 **Viewpoint**
Jobpac Connect[™]

System Administration
Module Guide
Version: 1.0

Document Control Table

Prepared by	Damien Bourke
Approved or authorised by	
Release date	30/04/2022
Version	1.0
Commercial in Confidence	

Change History

Version	Date	Author	Description of Changes
1.0	30/04/2022	DMB	Initial Release

Table of Contents

- Introduction..... 8**
 - Aim of this Reference Guide 8
 - The Role of the System Administrator 8
 - Pre-Requisites 8
 - Warning..... 8
- The Structure of the Jobpac System 9**
 - Definition of a Firm 9
 - Definition of a Work ID 9
 - Build a new Database..... 9
 - Maintain Work ID..... 10
 - Creating System Parameters..... 12
 - System Parameter Maintenance 12
 - Creation of Cost Types and GL links..... 14
- Parameter Listings..... 16**
 - Mandatory Control Accounts..... 16
 - Optional - User Definable Descriptions 17
 - Accounting Periods 18
 - Primary and Secondary Bank Accounts 18
 - Accounting Period Names..... 19
 - Period Conversion Codes 19
 - Period Conversion Factor..... 20
 - Account Types..... 20
 - Profit and Loss Transfer 21
 - Default Bank Charges General Ledger Account 21
 - Subcontractor Claims Paid Through Pending Invoices 21
 - Job Security 21
 - Approved Variation Transfer 21
 - Adjust Purchase Order Committed Budgets..... 22
 - Override Default Expense Account..... 22
 - General Ledger Back Posting Period 22

- General Ledger Posting to previous Financial Year 22
- Audit Trail Batch Numbers 23
- Automatically Print Audit Trails 23
- Individual Job Rollover 23
- Reduce Committed Budget 24
- General Ledger (GL) Chart of Accounts Structure 24
- General Ledger (GL) Security Function 25
- Unapproved Variation Transfer 25
- Negative Budget..... 25
- Posting Of Subcontract Authorities with Zero Value 25
- Margin Transfers 26
- Budget Finalisation..... 26
- Minimum \$ Amount for Accounts Payable “Terms” Cheque Run 26
- General Ledger Account for Discounts Earned 26
- Settlement Discount Facility 26
- Revenue Journals 27
- Default GL Revenue Account 27
- Auto Job Default 27
- Cost Centre Deletion..... 27
- Default PMW Formula 27
- Purchase Order Printing - Company Details 28
- Alternate Address on Cheque 28
- GST (Goods and Services Tax) Parameters 29
- Generic Parameters..... 30**
- Purchase Order Defaults 30
- Next Purchase Order Number..... 32
- AP Transaction Entry Details 32
- Accounts Payable (AP) Transaction Entry Defaults..... 33
- Subcontract Defaults..... 35
- GL Validation Parameters 38**
- Profit Centre 38
- Account Group..... 38

- Record Type 38
- System Parameter Reports 39**
 - List System Parameters 39
 - List PO Parameters 39
 - List AP Parameters 39
 - List SC Parameters 39
 - List Workids 39
- Copying 41**
 - Copying BAS & GST Codes 41
 - Copying Creditors 41
- User Security 42**
 - Create a New User 42
 - Defining User Access to a Work ID 42
 - For a New User, 43
 - For an Existing User 43
 - Defining Job Security within a Work ID 44
 - Enrol Users in CMS (Customizable Menu System) 45
 - General Ledger Access 45
 - List Jobpac Access 47
- Payroll Security 48**
 - Payroll Security Levels 48
 - Grant Payroll Access 49
- Central Security 51**
 - Central Security Access 51
 - Access Management 52
 - Job Setup Access 52
 - Maintain Budget Approvals 54
- Design Menus 56**
- Maintain CMS User Message 57**
 - List Current CMS Users 57
- Display Active Licence Users 58**
- Database Integrity 59**

- Database Integrity Checks..... 59
- Check for GL Batches Out of Balance..... 59
- Rebuild GL Summary Only 59
- 3 Way Cost of WIP Comparison Report 59
- Set Integrity Level 59
- Utilities 60**
- Unvoid a Cheque..... 60
- Reset a Payment Run 60
- Reset Subcontract 61
- Set Cost Centres To 61
- Clear EFT Consolidation/EFT Cancellation/Payment Run 62
- Validate Email Addresses 62
- Unfinalise Budget..... 62
- Change a Subcontract Value 62
- Bulk Cost Centre Delete 63
- Configure Modules 64**
- Accounts Receivable 64
- Follow-Up Actions..... 64
- Job Costing 64
- Job Types 64
- Resource Code Master List 65
- Assign Work Order Approval Levels 66
- Maintain Departments 66
- Define Schedule Intervals 67
- Register Type Maintenance..... 68
- Setup Bank Guarantee Status..... 69
- Reporting Units..... 69
- Reporting Sub Units..... 69
- Job Group Codes..... 70
- Set Retention Percentage Ranges 70
- Job User Definable Fields..... 71
- General Ledger..... 71

- Consolidations Define Levels 71
- Consolidations Define Account Summaries..... 72
- Consolidations Apply Definitions..... 72
- Intercompany Control Parameters..... 73
- Exchange Rate Maintenance 75
- ETS & Billing 75
- Standard Text Maintenance..... 75
- Maintain Value Limits 76
- Document Set Maintenance 76
- Location Security Maintenance 76
- Payment Schedule Header/Footer/Reason Codes 77
 - Maintain Creditor Type..... 78
- Workflow..... 78
 - Event Maintenance..... 78
- Maintain Email Addresses..... 79
- JOM Forms Module..... 80
 - Forms Maintenance..... 80
 - Forms By User 80
- Procurement Approvals 81
- BFM Utilities 82**

Introduction

Aim of this Reference Guide

The purpose of this Reference Guide is to assist System Administrators, and those users who are involved in the creation and maintenance of Work ID's in the Jobpac system. This Reference Guide will assist all to understand and apply the method and creation sequence when entering and maintaining Work ID's.

The Role of the System Administrator

The role of the System Administrator is fundamental to the efficient operation of the Jobpac system. The system administrator is responsible for:

- Creation and maintenance of new Work ID'S
- Controlling the use of the system by Jobpac Users
- Applying parameters to achieve the correct operation of the system
- Acting as a point of contact with Jobpac consultants and support staff

Pre-Requisites

- An understanding of the navigation of Jobpac screens
- An understanding of the organisation's system parameters,
- Chart of Accounts and
- Job structure

Warning

- Extreme caution should be undertaken when changing/applying parameters as different combinations may impact the processes currently in operation
- It is strongly recommended that any changes are done in consult with your Jobpac Consultant

The Structure of the Jobpac System

A combination of the following elements forms the basis of the Jobpac system:

- The Jobpac Program Library, containing all of the programs required to run Jobpac
- The System Control Files, containing information about the configuration of the system. These files contain information about which file groups are used, which firms are contained in the databases and which Work ID's are defined for each firm
- Database File Groups, containing user information entered using Jobpac. These are the files in which user entered data is stored. Each file group is contained in a separate library within Jobpac

Definition of a Firm

A firm is defined as an independent processing entity with its own Chart of Accounts and Master Files e.g., Creditors file, Debtors file etc. The Firm is identified by a combination of the Firm Code and the Database in the Work ID maintenance program.

Definition of a Work ID

Within each firm there may be several or many operational units. These units can be distinguished by one factor – the way that Jobpac programs operate can be different in each of them. This is achieved by giving each of these units a unique Work ID. A Work ID is the combination of the Database, the Firm Code and the Program Set Up Code.

Note: Work ID's may be Divisions of an organisation, geographically separated Branches or discrete legal entities.


Build a new Database

After your initial implementation it would be unusual to need to create a new database on Jobpac, as such **please talk to your Jobpac consultant prior to completing any of these steps to ensure that this is the best solution for the outcome you desire.**

From the Jobpac Main Menu screen, above, select

> System Administration > Define Companies > Build New Database.

CHECK WITH OH SOO



Create JOBPAC Database Files

You will be asked to confirm the Template Library that you wish to copy from, this will default to your existing Database.

Next you will need to enter the name of the new Database library.

You then need to decide if you wish to copy the data from the template library to the new library.

Select Create Library and OK to confirm.

The job will be submitted for batch processing in background if the Submit Job to Batch option is ticked, otherwise the process will be run interactively. For efficiency of processing take the default option which is to submit to batch. Pressing OK will initiate the process.

Maintain Work ID

As defined above, a Work ID is a separate operational unit. To create these units within the Jobpac system they must be identified and created as Work ID's.

There is a mandatory sequence that must be followed when Work ID's are created:

1. Defining a Work ID, including the database, firm code and Program Set Up
2. The creation of set of System Parameters
3. The creation of a Chart of Accounts
4. The creation of Intercompany Accounting and Reporting relationships
5. The creation of access rules and security for Jobpac Users
6. The creation of Cost Types and the entering of a link to the General Ledger accounts
7. The creation of GST and BAS Codes

*Note: The creation of **System Parameters**, the **Chart of Accounts** and the **GST and BAS Codes** may be done using "COPY" functionality within the Jobpac system, then editing as necessary.*

After Work ID's have been created following the above sequence, the Work ID is then ready to become operational. It is at this point that the Jobpac Master Files can be loaded.

These files include the Job, Creditors and Debtors master information. This can be done manually or by using copy functionality within Jobpac.

From the Jobpac Main Menu screen, above, select

> System Administration > Define Companies > Maintain Work ids

Work Id	Screen Name	Data Library	Firm Code	Program Setup Code	Seq Nbr	Production/Test	Disable
10	DMB Holding company	JDDMBDTA01	10	01	100	P	
20	DMB Sydney	JDDMBDTA01	20	01	200	P	
30	DMB Victoria	JDDMBDTA01	30	01	300	P	
40	DMB Queensland	JDDMBDTA01	40	01	400	P	
50	DMB ACT	JDDMBDTA01	50	01	500	P	
55	DMB SA	JDDMBDTA01	55	01	550	P	
60	DMB Training No 1	JDDMBDTA01	60	01	600	P	
70	DMB Training No 2	JDDMBDTA01	70	01	700	P	
910	**TEST** DMB Holding Company	JDDMBTST01	10	01	910	T	
920	**TEST** DMB Sydney	JDDMBTST01	20	01	920	T	
930	**TEST** DMB Victoria	JDDMBTST01	30	01	930	T	
940	**TEST** DMB Queensland	JDDMBTST01	40	01	940	T	
950	**TEST** DMB ACT	JDDMBTST01	50	01	950	T	
955	**TEST** DMB SA	JDDMBTST01	55	01	955	T	
960	Training Workid 960	JDDMBTST01	60	01	960	T	
970	Training Workid 970	JDDMBTST01	70	01	960	T	

Field Name	Description
Work ID	This is the number of the new Work ID. Only if creating a new workid.
Screen Name	Enter the name of the Work ID to appear on the main menu
Data File Library	Enter the Data library Name. This will generally be the same other existing Production Work ID's
Firm Code	Enter the two character Firm code for this workid
Program Set Up Code	Enter the 2 character program code. Generally use 01. This function is rarely used any more.
Sequence No	This is the sequence you want these workids to appear in lookup screens.
Production or Test	Set this to P for a production library, or T for a test Library. This is a mandatory field.
Disable	Leave blank, or enter Y if you wish to disable this workid. It will still appear in the lookup screens but cannot be selected.

Creating System Parameters

System parameters are used to allow for flexibility within the Jobpac system. Sets of parameters determine how various modules perform and define other functions within Jobpac such as user access, authority levels etc.


When setting up a new Workid, the parameters can be copied from another similar workid, and then modified as required.

If this is the first workid, your Jobpac Consultant will provide a standard list of parameters.

Note: Each parameter may be either alphanumeric or numeric. They may include dates, accounts codes or Y/N decisions.

From the Jobpac Main Menu screen, above, select:

> System Administration > Define Companies > Duplicate Parameters



Enter the code of the Work ID that you want to copy the System Parameters from. You need to be in the new Work ID that you wish to copy the parameters to.

Note: This should be a Work ID that performs the same functions as the new Work ID and one where Jobpac is used in the same way. If an identical match is not available, copy a Work ID that is substantially the same and add or edit parameters as necessary.

System Parameter Maintenance

Note: Adding, Deleting and Modifying a system parameter will change the operation of Jobpac. Note also that there are some parameters that set in conjunction with other parameters and that changing one parameter may affect the way another parameter is to be set up. Refer to your Jobpac consultant for any advice in this area.

To search the parameters, from the Jobpac Main Menu screen, above, select

> System Administration > Define Companies > Maintain Parameters

Then you need to enter the appropriate flags into the parameter. There may be a number of Sub Parameters for each main parameter.

System Parameter Maintenance - Details
ACTIONS OK BACK

Parm Code ACTCST Actual Cost Report Parameters

Parm Value

Work Id 920 **TEST** DMB Sydney

Type *ALPHA

< > ...

Field#	Type	Description	Str	Len	Alphanumeric	Number
01	*ALPHA	Hide Full total line in CSV	1	1	<input type="text"/>	
02	*ALPHA	Hide Reference field in CSV	2	1		
03	*ALPHA	Hide Activity field in CSV	3	1		
04	*ALPHA	Hide Description field in CSV	4	1		
05	*ALPHA	Hide Paid to Date field in CSV	5	1		

Creation of Cost Types and GL links

In Jobpac Cost Centres are shown as a combination of Cost Type and Cost Code. Cost Types are set up through the Jobpac Menu. Select:

> System Administration > Define Companies > Cost Types

Cost Types Maintenance
ACTIONS OK BACK

Please choose an action:

+ Initialize Cost Types

👁️ View Cost Types

✎️ Modify/Add Cost Types

Select the first option to enter new cost types.

The GL accounts that are linked here must be setup first.

Cost Types Maintenance
ACTIONS OK BACK

Mode Modify

	Description	Abbreviation	Default Expense Account	Account Description	Parameter Description
1.	<input type="text" value="Labour"/>	<input type="text" value="LB"/>	<input type="text" value="10008001"/>	Labour	
2.	<input type="text" value="Material"/>	<input type="text" value="MT"/>	<input type="text" value="10008002"/>	Materials	
3.	<input type="text" value="Subcontract"/>	<input type="text" value="SC"/>	<input type="text" value="10008004"/>	Subcontract	
4.	<input type="text" value="Plant"/>	<input type="text" value="PL"/>	<input type="text" value="10008003"/>	Plant	
5.	<input type="text" value="Other"/>	<input type="text" value="OT"/>	<input type="text" value="10008005"/>	Other	
6.	<input type="text" value="Revenue"/>	<input type="text" value="RV"/>	<input type="text" value="10006005"/>	Small Order Revenue	
7.	<input type="text"/>	<input type="text"/>	<input type="text"/>		
8.	<input type="text"/>	<input type="text"/>	<input type="text"/>		
9.	<input type="text"/>	<input type="text"/>	<input type="text"/>		
10.	<input type="text"/>	<input type="text"/>	<input type="text"/>		

System Administration

If the Cost Types are being created for the first time then the program will display the table used to set up the transactions permitted for each cost type.

Cost Types Maintenance										
⌵ ACTIONS ✔ OK ⏪ BACK										
Mode Modify										
Cost Type	LB	MT	SC	PL	OT	RV				
Description	Labour	Material	Subcontract	Plant	Other	Revenue				
AP Transaction Entry	<input type="text" value="Y"/>	<input type="text" value="Y"/>	<input type="text" value="Y"/>	<input type="text" value="Y"/>	<input type="text" value="Y"/>	<input type="text" value="N"/>	<input type="text" value="N"/>	<input type="text" value="N"/>	<input type="text" value="N"/>	<input type="text" value="N"/>
Purchase Orders	<input type="text" value="Y"/>	<input type="text" value="Y"/>	<input type="text" value="Y"/>	<input type="text" value="Y"/>	<input type="text" value="Y"/>	<input type="text" value="N"/>	<input type="text" value="N"/>	<input type="text" value="N"/>	<input type="text" value="N"/>	<input type="text" value="N"/>
S/C Agreements	<input type="text" value="Y"/>	<input type="text" value="N"/>	<input type="text" value="Y"/>	<input type="text" value="N"/>	<input type="text" value="N"/>	<input type="text" value="N"/>	<input type="text" value="N"/>	<input type="text" value="N"/>	<input type="text" value="N"/>	<input type="text" value="N"/>
Timesheet Entry	<input type="text" value="L"/>	<input type="text" value="L"/>	<input type="text" value="N"/>	<input type="text" value="N"/>	<input type="text" value="N"/>	<input type="text" value="N"/>	<input type="text" value="N"/>	<input type="text" value="N"/>	<input type="text" value="N"/>	<input type="text" value="N"/>
GL Prompt Cheques	<input type="text" value="Y"/>	<input type="text" value="Y"/>	<input type="text" value="Y"/>	<input type="text" value="Y"/>	<input type="text" value="Y"/>	<input type="text" value="N"/>	<input type="text" value="N"/>	<input type="text" value="N"/>	<input type="text" value="N"/>	<input type="text" value="N"/>
Job Journal Entry	<input type="text" value="Y"/>	<input type="text" value="Y"/>	<input type="text" value="Y"/>	<input type="text" value="Y"/>	<input type="text" value="Y"/>	<input type="text" value="N"/>	<input type="text" value="N"/>	<input type="text" value="N"/>	<input type="text" value="N"/>	<input type="text" value="N"/>
Accounts Receivable	<input type="text" value="N"/>	<input type="text" value="N"/>	<input type="text" value="N"/>	<input type="text" value="N"/>	<input type="text" value="N"/>	<input type="text" value="Y"/>	<input type="text" value="N"/>	<input type="text" value="N"/>	<input type="text" value="N"/>	<input type="text" value="N"/>

Enter above: 'Y' - if the program can update that cost type
 'N' - if it cannot update that cost type
 'L' - for Labour

It is advisable to talk to your Jobpac consultant prior to completing this step or making changes to ensure that the changes meet the processing requirements and restrictions suitable for the company.

The next step is to return to the Modify option and select the Revenue Account Function. This sets up the default revenue accounts for the company or Group Code.

Note that the revenue categories are pre-defined and are consistent with revenue accounting functions in other areas of Jobpac such as the BFM. Allocate General Ledger accounts to the categories in accordance with the function set out in the table, even if there is no current expectation that the accounts will be used.

Cost Type Maintenance			
⌵ ACTIONS ✔ OK ⏪ BACK			
Mode Modify			
Group Code			
Revenue Categories	Revenue Account		
Sundry Revenue	<input type="text" value="10006010"/>	<input type="text" value="⌵"/>	Sundry Contract Revenue
Contract Works	<input type="text" value="10006001"/>	<input type="text" value="⌵"/>	Contract Works revenue
Materials on / off site	<input type="text" value="10006001"/>	<input type="text" value="⌵"/>	Contract Works revenue
Variations	<input type="text" value="10006003"/>	<input type="text" value="⌵"/>	Variations revenue
Rise & Fall	<input type="text" value="10006001"/>	<input type="text" value="⌵"/>	Contract Works revenue
Nominated Subcontractors	<input type="text" value="10006001"/>	<input type="text" value="⌵"/>	Contract Works revenue
PC Sums / Engineers Contingency	<input type="text" value="10006001"/>	<input type="text" value="⌵"/>	Contract Works revenue
Bonus / LDs	<input type="text" value="10006001"/>	<input type="text" value="⌵"/>	Contract Works revenue

If you are using Job Group codes, then default GL accounts can be established for each Group code.

Parameter Listings

Note: The following Parameter descriptions are only a sample of the parameters that are contained within Jobpac, but these are the parameters that make basic operation available. A complete list of parameters is available from Jobpac consultants. Consulting assistance may be required to review the impact of combining more complex parameters.

It should be remembered that as new modules are implemented into an organisation the parameters will have to be reviewed and amended or added to as required

Parameters can be grouped to provide access and functionality within modules. The parameters relating to core modules are listed below

Mandatory Control Accounts

These parameters provide Jobpac with the account numbers for important control accounts. These control accounts are used by the system for one half of the double-sided journal entries. The maximum length of an account number is 10 characters.

Mandatory Control Accounts

Symbol	Description
RETERN	GL Account code for Retained Earnings (Profit/Loss)
STOCK	GL Account code for Stock on Hand
TRCRED	GL Account code for Trade Creditors Control
SCCRED	GL Account code for Subcontractors Credit Control
TCRETN	GL Account code for Trade Creditors Retention
SCRETN	GL Account code for Subcontractors Creditor Retentions
TRDEBT	GL Account code for Trade Debtors Control
RTNHLD	GL Account code for Retentions Held
PRFTLS	GL Account code for Profit and Loss Control

Optional - User Definable Descriptions

User definable descriptions allow the system administrator to define the description which will be placed next to the User Definable fields in the master file maintenance programs. User definable descriptions (UDD) may be up to 15 characters long.

Optional - User Definable Descriptions

Symbol	Description
CCUDF1	UDD #1 for Cost Codes
CCUDF2	UDD #2 for Cost Codes
CCUDF3	UDD #3 for Cost Codes
CCUDF4	UDD #4 for Cost Codes
CCUDF5	UDD #5 for Cost Codes
CRUDF1	UDD #1 for Creditors Master File
CRUDF2	UDD #2 for Creditors Master File
DBUDF1	UDD #1 for Debtors Master File
DBUDF2	UDD #2 for Debtors Master File
GLUDF1	UDD #1 for General Ledger
JIUDF1	UDD #1 for Jobs Master File
JIUDF2	UDD #2 for Jobs Master File
OHUDF1	UDD #1 for Purchase Orders Header
OHUDF2	UDD #2 for Purchase Orders Header
OIUDF1	UDD #1 for Purchase Order Items
OIUDF2	UDD #2 for Purchase Order Items
PMUDF1	UDD #1 for Plant Items
PMUDF2	UDD #2 for Plant Items
PRUDF1	UDD #1 for Employees
PRUDF2	UDD #2 for Employees
SCUDF1	UDD #1 for Subcontracts
SCUDF2	UDD #2 for Subcontracts

Symbol	Description
SCUDF5	UDD #5 for Subcontracts

Accounting Periods

To ensure that Financial transactions are posted to the correct accounting period, the Accounting Period parameters must be correctly set. Accounting periods are entered in the format – YYYYMM.

*Note: Accounting periods are based on Financial Year not Calendar Year, and are driven by the parameter **FACTOR**. This parameter is a number representing the last month of the financial year.*

If FACTOR = 6, then JUNE is the last month of the Financial year. So 202201 would be JULY 22

If FACTOR = 3, then MARCH is the last month of the Financial year. So 202201 would be APRIL 22

Accounting Periods

The standard in Jobpac is that 2021 represents the year financial year 2021/2022

Term	Definition
GLAP	Accounting Period for the General Ledger
APAP	Accounting Period for Accounts Payable
ARAP	Accounting Period for Accounts Receivable
JCAP	Accounting Period for Job Costing
STKAP	Accounting Period for Stores Control

Note: Once set these parameters appear on the main menu screen of Jobpac so that the current accounting periods for the Work ID can be readily identified.

Primary and Secondary Bank Accounts

The Primary and Secondary Bank Accounts have a maximum length of 25 characters, the first 10 indicating the GL Account and the next 15 indicating the bank account number.

Bank Accounts

Account	Description
CASH	Primary Bank Account GL code and Bank A/c number
CASH01	Secondary Bank Account GL code and Bank A/c number

Note: If required, it is possible to have additional Bank Accounts defined and numbered up to CASH99.

*Bank Accounts are now managed by the menu item **Cash Account Maintenance***

Accounting Period Names

It is necessary to define the names of the months that correspond to the accounting periods. For a financial year from 1 July to 30 June, this would be the example as below.

Account Period Table

Month	Month Name
MTH01	July
MTH02	August
MTH03	September
MTH04	October
MTH05	November
MTH06	December
MTH07	January
MTH08	February
MTH09	March
MTH10	April
MTH11	May
MTH12	June

Period Conversion Codes

Accounting periods are always displayed in the format MMM99, where MMM is a 3 character abbreviation for the month, and 99 is the year. The twelve 3 character codes are all entered with this parameter, and the first should correspond to the first accounting period of your organisation's financial year. Parameter Name is PCONV.

Period Conversion Tables

Term	Definition
PCONV	Period Conversion Codes

For a July to June financial year the parameter will be:-

Period Conversion Factor

This factor is used as a conversion between the calendar month and the financial period. A value between 0 and 11 should be entered (e.g. for July-June financial years, the correct value is 6; or for April-March financial years, the correct value is 3). Parameter Name is FACTOR.

Period Conversion Table

Conversion Value	Financial Year Period
0	January to December Financial Year
1	February to January Financial Year
3	April to March Financial Year
6	July to June Financial Year
9	October to September Financial Year

Account Types

Account Type descriptions will be used on all GL reports. These descriptions can be up to 30 characters in length. The account types are fixed within Jobpac but the descriptions can be changed. The suggested values are:

Suggested Value and corresponding Account Type Description

Suggested Value	Account Type Description
ATYP1	Current Assets
ATYP2	Non-current Assets
ATYP3	Current Liabilities
ATYP4	Non-current Liabilities
ATYP5	Capital Accounts
ATYP6	Direct Revenue
ATYP7	Indirect Revenue
ATYP8	Direct Expense
ATYP9	Indirect Expense

Profit and Loss Transfer

Profits (or Losses) may be transferred to the Retained Earnings account on a monthly or yearly basis.

Profit & Loss Transfer frequency

PLXFER	Transferred to Retained Earnings account
M	Monthly
Y	Yearly (Recommended)

Default Bank Charges General Ledger Account

This is the default bank charges account used by the Direct Debit Entry program in the Bank Reconciliation.

Bank charges	Account Number
BNKCHG	Default GL account number

Subcontractor Claims Paid Through Pending Invoices

This parameter is used to indicate (Y/N) whether the claims from subcontractors will be processed through the pending invoices facility. If the facility is used, a window of all invoices related to the subcontractor and not assigned to a Purchase Order will be displayed in the subcontract payment authorisation program to enable the selection of the invoice(s) being processed. Once the invoice is selected, that invoice will not be available for selection in the AP transaction entry program.

SCPINV	Subcontractors Claims
Y	Claims from Subcontractors will be process through the Jobpac Pending Invoices facility.
N	Claims from Subcontractors will not be processed through the Jobpac Pending Invoices facility.

Job Security

This parameter indicates whether job level security is activated. This is the method by which a job can only be viewed by certain employees with the correct access within Jobpac.

JOBSEC	Settings
Yes/No (Y/N)	Y (Yes) can only be viewed by employees with appropriate access or N (No) Job Level Security has not been activated and can be viewed by all.

Approved Variation Transfer

If activated, the system will automatically transfer a variation to Job costing when client approval is gained.

VRAPTR Transfer variation to Jobcosting

Y Yes, Automatic Transfer is active

N No, not active.

Adjust Purchase Order Committed Budgets

This parameter determines whether committed budget values are adjusted to include completed Purchase Orders.

Note: A completed Purchase Order is one that has been fully received and paid. The budget will be adjusted by the amount of the paid invoice. This parameter can be overridden at Job Maintenance level.

COMBUD Purchase Order to Committed Budgets

Y Yes, The budget will be adjusted by the amount of the paid invoice

N No, not active.

Override Default Expense Account

This parameter is used to determine whether to allow the override of the default expense account nominated for the Job Cost Type in both the AP Transaction Entry and the Journal Entry programs.

ACENTR Permission TO OVERRIDE Default Expense Account

Y Yes, Override of the default expense account is allowed

N No, Override of the default expense account is not allowed.

General Ledger Back Posting Period

This parameter is used to nominate the number of accounting periods allowed for General Ledger back posting. The number range is 0-999.

PSTBCK Number of Accounting Periods

0-999 Number of accounting periods possible

General Ledger Posting to previous Financial Year

This parameter controls the General Ledger posting to the previous financial year.

PSTLYR Posting to previous financial year

Y Yes, Posting to the previous financial year enabled

N No, posting to the previous financial year not possible.

Audit Trail Batch Numbers

All financial programs log the transactions to a central system audit file in a batch format. The parameter settings are counters and start at 0001 with a nominated prefix. The exception is the Accounts Payable Cheque batch that starts at 1001.

Batch	Description	Batch Number Range
BATDDB	Direct Debit Entry batch number	B0001
BATHIT	Subcontract Accrual Held in Trust Batch Number NO LONGER USED	H0001
BATCHQ	Accounts Payable Cheques batch number	P1001
BATARR	Cash Receipts batch number	R0001
BATARI	Accounts Receivable Transaction batch number	D0001
BATAPT	Accounts Payable Transaction batch number	C0001
BATSCA	Subcontract Agreement Posted batch number	A0001
BATCLM	Uncertified Progress Claim batch numbers	U0001
BATPAY	Payroll Transaction batch number	Y0001
BATPLT	Plant Transaction batch number	L0001
BATTST	Timesheet Posting batch number	Y0001
BATSTK	Stores Control Transaction batch number	I0001
BATCHS	Sundry Cheques batch number	P0001
BATJNL	Journal Entry batch number	J0001

Automatically Print Audit Trails

This parameter controls the automatic print of audit trails.

AUDPRN	Configured to Automatically Print Audit Trails
Y	YES All audit trails will print automatically
N	No, audit reports will print only on request using the system audit report printing facility.

Individual Job Rollover

This parameter controls the rolling over of jobs at month-end.

NO LONGER USED

JOBROL	Configured to Automatically roll over all or selected jobs
--------	------------------------------------------------------------

Y	YES Selected Jobs or a range of jobs can be individually rolled
---	-----------------------------------------------------------------

N	No All jobs will be rolled (default)
---	--------------------------------------

Reduce Committed Budget

This parameter is used with formulas "C" and "E" in the Project Manager's Worksheet.

Note:

Formula C:

F.C.C. = Old FCC + Sum of Worksheet Entries

F.F.C. = Committed Costs + New FCC

Formula E:

F.C.C. = Sum of Worksheet Entries

F.F.C. = Committed Costs + FCC

REDCOM	Reduce Committed Budget
--------	-------------------------

Y	YES The Committed Budget is reduced by the difference between the new FCC and the current FCC.
---	------------------------------------------------------------------------------------------------

N	No, The committed budget is not reduced
---	-----------------------------------------

General Ledger (GL) Chart of Accounts Structure

This parameter is used to nominate the two character positions of the General Ledger Chart of Accounts structure. This structure is used to control the GL security for the GL Detail Report and the Enquiry programs.

GLSTRP	GL Chart of Accounts Structure
--------	--------------------------------

01-01	State
-------	-------

02-04	Department
-------	------------

05-08	Main Account
-------	--------------

09-10	Location
-------	----------

Note: With the account structure listed above, the starting position in the account number of the state code is 1, the department 2, main account 5 and location 9. Therefore the parameter would be set to 01020509.

General Ledger (GL) Security Function

This parameter controls the General Ledger security function

GLASEC	Configured for General Ledger Security Function
Yes/No (Y/N)	Position one, Y (Yes) GL Security –restricting access to authorized users is activated or N (No) is not activated
Yes/No (Y/N)	Position two, Y (Yes) allows access to view job actual or N (No) does not. If left blank assumes Yes.
GLASEC	YY

Unapproved Variation Transfer

This parameter controls whether unapproved variations can be transferred.

UNVRTR	Configured TO allow Unapproved Variation Transfer
Y	YES Transfer unapproved variations
N	No Will not transfer unapproved variations

Negative Budget

If activated, the system will allow variations to cause a negative budget.

NEGBUD	Variations to cause negative budget
Y	YES allow negative budget (Recommended)
N	No Will not allow negative budget

Posting Of Subcontract Authorities with Zero Value

This parameter controls the posting of Authorities with zero value in the Subcontract Payment Authority Posting program.

PSTZER	Subcontract Payment Authority Posting
Y	YES Post Authorities with zero value
N	No Will not post Authorities with zero value

Margin Transfers

This parameter controls margin transfers in the Budget Transfer program.

ADJMRG	Margin Transfers
Y	YES Margin transfers permitted
N	No Will not allow Margin transfers

Budget Finalisation

This parameter controls the budget finalisation for jobs with non-zero undistributed budgets.

BFINUB	Budget Finalisation
Y	YES Budget finalization is permitted for any job
N	No Budget finalization is not allowed for jobs with non-zero current budgets

Minimum \$ Amount for Accounts Payable “Terms” Cheque Run

This parameter is used to nominate the minimum dollar amount to prevent cheques below this amount being printed on an Accounts Payable "Terms" cheque run.

MINCHQ	Minimum Dollar Amount for AP “Terms” Cheque Run

Note: Cheques below this amount can be printed using the "Prompt Payment" cheque run. A report of cheques below this amount will be printed as part of the "Cheque Preview" run.

General Ledger Account for Discounts Earned

This parameter is used to nominate the General Ledger account for discounts earned. The account MUST be nominated if the Settlement Discount Facility is used. All the discounts earned will be posted to this account in the General Ledger.

APSDGL	GL Account for Discounts Earned

Settlement Discount Facility

This parameter controls the setting of the settlement discount facility for the company.

SETDSC	Settlement Discount Facility
Y	YES Settlement discount facility is enabled
N	No Settlement discount facility is disabled

Revenue Journals

This parameter controls the use of revenue journals, journals with a job number and no cost centre.

REVJNL	Revenue Journals
Y	YES System is configured to use Revenue Journals
N	No System will NOT use Revenue Journals

Default GL Revenue Account

This parameter is used by the progress claim entry program to get the GL account code for the revenue account. The value may be overridden at job levels or entry time.

REVGLA	Default GL Revenue Account

Auto Job Default

This parameter controls the setting of the automatic job default. Indicates if the system will automatically retrieve the last job number used by the user.

AJD	
Y	YES Automatic job default is activated
N	No Automatic job default NOT activated

Note: This Auto Job Default facility allows each user to have the last job used as the default job in all non-accounting maintenance, transaction processing and report bounding screen programs.

Cost Centre Deletion

This parameter controls the deletion of Cost Centres which have non-zero budgets in the Cost Centre Deletion program.

DELBUD	
Y	YES Delete cost centres with non-zero budgets
N	No Do NOT delete cost centers with non-zero budgets

Default PMW Formula

This parameter is used as the default Project Manager's Worksheet formula for the new jobs set up in the Jobs Maintenance program.

PMWDFT Default PMW Formula

PMW formula definitions

Formula	Definition	Defintion 2
B	F.C.C. = Uncommitted Budget + Sum of Worksheet Entri...	F.F.C. = Committed Costs + FCC
E	F.C.C. = Sum of Worksheet Entries	F.F.C. = Committed Costs + FCC
G	F.C.C. = Your FFC Entry - Committed Costs	F.F.C. = Your Entry
H	F.C.C. = Sum of Worksheet Entries	F.F.C. = Cost Of WIP + FCC

PMWFRM02

Select Close

Project Manager Worksheet Formula Definitions

Purchase Order Printing - Company Details

In the Purchase Order printing facility the company name/address can be printed if stationery without company details is used.

Field Name	Description
CONAME	Company Name, maximum of 26 characters
COADR1	Company Address Line 1, maximum of 30 characters
COADR2	Company Address Line 2, maximum of 30 characters.
COADR3	Company Address Line 3, maximum of 30 characters
COACN	Company ACN, maximum of 15 characters
COTELN	Company Telephone number, maximum of 15 characters
COFAX	Company Fax number, maximum of 15 characters

Alternate Address on Cheque

This parameter determines which creditor address to use on the cheque. Also selects extended name of the creditor.

ALTADR	Alternate Address
Y	YES Print alternate creditor address on

N No Do not print alternate creditor address on cheque

GST (Goods and Services Tax) Parameters

There are a number of parameters that control the treatment of GST within Jobpac.

Parameters	Description
GSTDFT	The default GST Code to be used in all transactions
GSTIAM	GST Input accounting method
GSTICA	GST Input GL Control account
GSTOCA	GST Output GL Control account
GSTREG	GST Registration number of the company
GSTNAM	Nominate the abbreviation of the tax applicable to your country (e.g.: GST, VAT...)

Generic Parameters

Generic parameters are used to allow a separate parameter to be entered for each Work ID with a firm code. They are created by combining a three-digit code (e.g. ORD) with the Program Setup Code for the nominated Work ID. Each generic parameter provides a string of sub-parameters which are used to influence the operations of various programs.

Purchase Order Defaults

Both the Purchase Order Maintenance and the Delivery Docket programs use this parameter. This parameter provides a number of sub-parameters. Described below are the system defaults, should you require any further configuration of this area please discuss with your Jobpac consultant.

Parm Code	Tp	WId	Parameter Description	Alphanumeric	Num 01	Num 02	Num 03	Num 04	Num 05
ORDXX	A	621	Purchase Order related to printing	1NY\$YY NNYNNYY NN					
ORD01	A	666	Purchase Order entry parameters.	1NY\$YYP0YYYYNYNY NY Y8					
ORD01	A	700	Purchase Order entry parameters.	1NY\$Y70YYYYNYNY NY Y					
ORD01	A	710	Purchase Order entry parameters.	1NY\$Y71YYYYNYNY NYN YY Y					
ORD01	A	720	Purchase Order entry parameters.	1NY\$Y72YYYYNYNY NY Y					
ORD01	A	730	Purchase Order entry parameters.	1NY\$Y73YYYYNYNY NY Y					
ORD01	A	790	Purchase Order entry parameters.	1NY\$Y79YYYYNYNY NYN Y Y					
ORD01	A	800	Purchase Order entry parameters.	1NY\$YYP0YYYYNYNY NY Y8					
ORD01	A	996	Purchase Order entry parameters.	1NY\$Y70YYYYNYNY NY Y					

Purchase Order (PO) Entry Parameters

Note: ORDnn - Purchase order defaults 1NY\$YYxxYNYYYNYNYNbYNNNNYNNN

Field Number

Options

1=Default Allocation Code

1=Job allocation, 2=Job allocation, 3=Unallocated

2=Mandatory default allocation

Y = Mandatory – user cannot use other allocations
N = Not mandatory

3=Unallocated orders allowed

Y = Job/Jobcard allocation fields may be left blank
N = Job/Jobcard allocation fields must be entered

4=Committed budget entry method

% = Committed budget entry method
\$ = Committed budgets entered as dollar values

Field Number	Options
5=Inventory prompt to be shown	Y = Prompt for 15 character inventory code N = Do NOT prompt
6=Automatic print description prompt	Y = Detailed descriptions will automatically be prompted N = Prompting requires a Function Key
7=Two Character Code	For automatically generated order numbers. These two characters must be used to set up the order number parameter GENxx. Refer to the description of "Next Purchase Order Number" in the following table.
8=Use order value as a substitute for committed budgets	Y = this is the default, if left blank the order value will be used instead of committed budget. N = Prompting requires command sequence
9=Enter incurred costs during Delivery Docket entry	Y = Incurred costs may be manually entered. N = Incurred costs may not be manually entered.
10=Print headings on PO	Y = Print headings N = Do not print headings
11=Print Company Name & Address on PO	Y = Print company name and address N = Do not print company name and address
12=Requisition at Item Level	Y= Allow entry of requisition number at PO item level. N= Standard setting of requisition at order header.
13=Prompt for Fax options	Y=Prompt for fax printing options N= No prompting – standard setting.
14=Prompt for printing conditions	Y=Prompt for printing N= No prompting – standard setting.
15=Default Job Code at order item	Y=Use default job to fill code while entering order items. N= No - standard setting.
16=Allow selection of delivery dockets in PO maintenance.	Y= Enable delivery docket entry as a selection option via order lines. N = Delivery dockets not allowed through PO maintenance.
17=No longer Used	
18=Clear cost centre in order item entry	Y=Clear cost code and cost type after entry of a PO line. N= Do not clear.
19= GST Value Entry Method	G=Gross value entry N=Nett value entry
20=Display and allow entry/update of ABN	Y=Allow entry and update of ABN during PO entry. N= Do not allow.
21=Delivery QTY>Order Qty	Y=Delivered Qty can be greater than Order Qty N= Delivered Qty must be less than or equal to Order Qty

Field Number	Options
22=Default GL account for overhead items.	Y= Retain previously entered GL account when entering items costed to GL overheads. N= Clear GL account on each new line.
23=NOT USED	
24=Allow negative order quantities	Y= Allow entry of negative PO values N= Entry of PO values must be positive.
25 and 26=NOT USED	
27=PO Print	Y=Print 'Total Excluding GST' line
28=NOT USED	
29=Received By Field	Y=Protect 'Received By' field in Delivery docket entry.
30=Check creditor product reference	Y= When a product code is entered, ensure that the product code is defined for the creditor code being processed. N = Do not check product code exists for current creditor.
31=Full Description	Y=Allow display of Full Description even if PO Item is complete
32=Override Job	Y=Allow Job No to be overridden in subsequent PO Items
33=T&Cs	Y=JOM form used for T&Cs
34=I/C	Y=Allow I/C costing on any workid linked to the Central workid
35=Not Used	

Next Purchase Order Number

The purchase order number is 8 characters and can be alphanumeric. The program will increment numeric values starting from the right-hand end of the parameter. Therefore if ORD00001 is used, 99999 orders may be entered before the number would be reused.

Note: GENxx- Next Purchase order number ORD00001

where "xx" is the 7th/8th characters nominated in the ORDnn parameter

AP Transaction Entry Details

Similar to Purchase Orders as detailed under Generic Parameters in this Reference Guide, Accounts Payable transactions have a number of parameters that control the operation of AP within Jobpac.

System Parameter Maintenance - Details							ACTIONS	OK	BACK
Parm Code	APT01 AP Transaction Entry Parameters		Work Id	920 **TEST** DMB Sydney					
Parm Value	JNNRYYY 3 Y		Type	*ALPHA					
< > ...									
Field#	Type	Description	Str	Len	Alphanumeric	Number			
01	*ALPHA	Default Cost Allocation, J=Job, "M"or " " = Jobcard or A	1	1	J				
02	*ALPHA	Retention used in A/P = 'Y'	2	1	N				
03	*ALPHA	Mandatory entry on PO number = 'Y'	3	1	N				
04	*ALPHA	PO number at detail line = 'Y'; PO number at header ...	4	1	N				
05	*ALPHA	Default invoice status for creditors = "R, H, or P"	5	1	R				
06	*ALPHA	Allow to invoice more than PO item value = 'Y'	6	1	Y				
07	*ALPHA	Use delivery docket matching = 'Y'	7	1	Y				
08	*ALPHA	Display and allow invoice on all PO items = 'Y'	8	1	Y				
09	*ALPHA	Create PO records if PO does not exist = 'Y'	9	1					
10	*ALPHA	Creditor or Subbie payment checked at transaction L...	10	1					
11	*ALPHA	Gross entry method = "G" on pending invoice	11	1					
12	*ALPHA	Initial cursor position on line entry - 1=Tax, 2=Qty, 3=	12	1	3				
13	*ALPHA	Invoice date Can't be greater than entry date = "Y"	13	1					
14	*ALPHA	Intercompany is not allowed = "Y"	14	1					
15	*ALPHA	GST is to be posted in the current workid = 'Y'	15	1					
16	*ALPHA	Allow input of 100% GST trasaction = 'Y'	16	1					
17	*ALPHA	Use I/C source workid for batch numbering = 'Y'	17	1					
18	*ALPHA	Allow to invoice more than PO item quantity = 'Y'	18	1	Y				
19	*ALPHA	Validate purchase order number	19	1					

Accounts Payable (AP) Transaction Entry Defaults

Note: Both the Accounts Payable Transaction Entry and the Creditor Maintenance programs use this parameter.

This parameter provides a number of sub-parameters. Described below are the system defaults, should you require any further configuration of this area please discuss with your Jobpac consultant.

APTnn- AP Transaction Entry defaults JYNNRYYY

Accounts Payable Entry position

Description

1= Default Allocation Code

J = Job allocation
M = Job card allocation

2=Prompt for Retention

Y = Prompt for Retention against each dissection
N = Retention cannot be entered

3=Purchase Order Required

Y = Purchase Order mandatory for each invoice
N = Purchase Order optional for each invoice

4=Purchase Order at Line Level

Y = Purchase Order/Item is prompted for at each invoice line
N = Purchase Order is prompted for at invoice header level.

Accounts Payable Entry position	Description
5=Default transaction status	R = Released H = Held P = Prepaid
6=Invoice may exceed PO value	Y=Allow value invoiced to exceed value raised on PO N= Do not allow
7=Use Delivery Docket Matching.	Y=If delivery docket are allow entry of invoice details to match docket. N= Do not use docket matching.
8=Use Full PO entry method.	Y= When PO entered at header level, the user will be shown a screen with all outstanding PO items for update. N= PO items will be matched at AP invoice dissection level using the normal screen processing.
9=Add Purchase Orders	Y= Automatically add a Purchase Order Header and items if order number specified and does not exist. N= Do not add PO
10=NOT USED	
11=NOT USED	
12=Cursor Position	Initial Cursor Position on dissection lines– "1" on Tax Code field "2" on Quantity field "3" on Gross Amount field "4" on Net Amount field.
13=Invoice date control	Y = Invoice date cannot be greater than current date of entry N= No checking
14=Intercompany Control	Y=Intercompany processing is not allowed N= Intercompany processing is allowed if active for this work id
15=GST Control	Y= Use current work-id for GST posting N= Use centralised GST posting
16=100% GST Transaction	Y=Allow a transaction to contain a value of 100% GST N=Do not allow
17=I/Coy Batch Numbering	Y=Use Intercompany source Work-ID for batch numbering.
18=Invoice More	Y=Invoice Qty can be greater than PO Item Qty
19=Validate PO	Y=If purchase order number entered should be Validated - valid PO and matching supplier.

Subcontract Defaults

Both the Subcontract Maintenance and the Subcontract Claim Processing programs use this parameter. This parameter provides a number of sub-parameters in use in Jobpac Release 7.0. Described below are the system defaults, should you require any further configuration of this area please discuss with your Jobpac consultant.

System Parameter Maintenance - Details							ACTIONS	OK	BACK
Parm Code	SBC01 Subcontracting entry parameters.			Work Id	920 **TEST** DMB Sydney				
Parm Value	SYLRYABY NNNYYY Y Y			Type	*ALPHA				
							<	>	...
Field#	Type	Description	Str	Len	Alphanumeric	Number			
01	*ALPHA	Committed budgets entered as \$ or %	1	1	\$				
02	*ALPHA	Substitute order value for committed budget Y or N	2	1	Y				
03	*ALPHA	Default Item Type L=Lump Sum, R=Schedule of Rates	3	1	L				
04	*ALPHA	Default claim status 'R' = released, 'H' = held	4	1	R				
05	*ALPHA	Print heading in subcontract order print (Y/N)	5	1	Y				
06	*ALPHA	Print company details on subcontract order print (Y/...	6	1	Y				
07	*ALPHA	Auto generate agreement # - Blank or 2 character pr...	7	2	AB				
09	*ALPHA	Allow extended item description (Y/N)	9	1	Y				
12	*ALPHA	Default for subject to rise & fall flag (Y/N)	12	1	N				
13	*ALPHA	Default for nominated SC falg (Y/N)	13	1	N				
14	*ALPHA	Default for paid direct flag (Y/N)	14	1	N				
15	*ALPHA	Default for update utility used flag	15	1	Y				
16	*ALPHA	Default valuation amt/qty to authorised amt/qty (Y/...	16	1	Y				
17	*ALPHA	Allow call to variation register from SAGPAYVR (Y/N)	17	1	Y				
18	*ALPHA	Enable site allowance values (Y/N)	18	1					
19	*ALPHA	If INSUPD called from SAGMNT disable mandatory fl...	19	1					
20	*ALPHA	Print "Purchase Order" or "Subcontract Order" in Fr...	20	1					
21	*ALPHA	Make Trade Code a mandatory field (Y/N)	21	1					
22	*ALPHA	Default Extended comp date to Original Comp date i...	22	1					
23	*ALPHA	RCTI flag protected (Y/N/C)	23	1					
25	*ALPHA	Automatic SOR number generation - 2 character prefix	25	2					
27	*ALPHA	Allow Update of Insurance details on Payment Auth ...	27	1	Y				
29	*ALPHA	Max Ret calculation method 1,2,3	29	1					
30	*ALPHA	Hold Payment at Authorisation Level (Y/N)	30	1					
31	*ALPHA	Payment authority date not to exceed date of entry (...)	31	1					
32	*ALPHA	Allow / Show Qty input (Y/N)	32	1					
33	*ALPHA	Allow Payment Date to be changed in SC Payment Au...	33	1					
34	*ALPHA	Allow printing of S/C payment Date on Authority (Y/N)	34	1	Y				
35	*ALPHA	Print Retention %, Max Retention & Bank Guarantee ...	35	1					
36	*ALPHA	Enable S/C Rating and Text in S/C Payment authoris...	36	1					

Subcontract entry position	Description
1= Committed Budget Entry Method	% = Committed budgets entered as percentages \$ = Committed budgets entered as dollar values
2= Use order value as a substitute for committed budgets	Y = (default) if left blank, the order value will be used instead of committed budget N = Order value will not be used
3= Default Item type	L = Lump Sum item R = Rated item
4=Default Claim Status	R = Released H = Held
5 & 6	The 5th and 6th Characters are no longer used (v7.0)
7 & 8	Two character code for automatically generated order numbers. These two characters must be used to set up the order number parameter GENxx
9 =Extended Description Entry	Y = Subcontract Maintenance program will display an additional screen for the extended description for the items. N = No, prompt for extended descriptions
10 & 11	The 11th and 12th Characters are reserved for customer specific programs.
12=Rise & Fall Flag	Contains the default value for Subject to Rise & Fall Flag of Y or N
13=Nominated SC Flag	Contains the default value for Nominated SC Flag of Y or N
14=Paid Direct Flag	Contains the default value for Paid Direct Flag of Y or N
15=Update Utility Used Flag	Contains the default value for Update Utility Used Flag of Y or N
16=SC Payment Valuations	Y=Default valuation amount/quantity to authorized amount/quantity. N=Do not default
17=Enable Variation Register	Y=Enable access to Variation Register from SC Maintenance N= Do not enable.
18=Site Allowance	Y= Enable update of site allowance values in SC Maintenance N= Do not allow updates
19=Insurance Updates	Y=Do not allow insurance updates from SC Maintenance. N=Allow update of insurance values from SC Maintenance
20=SC Front Sheet Title	P= Print "Purchase Order" on SC Front Sheet S= Print "Subcontract Order" on SC Front Sheet
21=Trade Code	Y=Trade Code is a mandatory feed in SC Maintenance N= Trade Code is optional
22=Extended Completion Date	Y=Default extended completion date to Original Completion Date if left blank. N=No default

Subcontract entry position	Description
23=RCTI Flag	<p>C=Protect value held in RCTI agreement flag. This will default from the Creditor</p> <p>Y= It will be protected regardless.</p> <p>N=Allow change of RCTI flag.</p>
25-26=SOR Agreement Number Gen	<p>Two character code for automatically generated order numbers. These two characters must be used to set up the order number parameter GENxx. This parameter allows setup of a different GENxx parameter specifically for Schedule of Rates agreements so that order type can be distinguished quickly from the order number.</p>
27=Insurance Details Update	<p>Y=Allow update of insurance details from SC Payment Authorisation.</p> <p>N=Do not allow.</p>
28=SC GST Posting	<p>Y=GST Posted to project work ID</p> <p>N=GST posted to central work ID</p> <p>Set Default Calculation Method for max retention.</p>
29=Retention Calculation	<p>1. Based on Original</p> <p>2. Based on Original + Approved Variations</p> <p>3. Based on Original + Approved Variations + Unapproved Variations.</p> <p>If Blank the method will default to 3.</p>
30=Hold Payments	<p>Y=Allow hold payment option at time of Payment Authorisation.</p> <p>N= Do not allow</p>
31=Payment Authority Date	<p>Y= Payment authority date cannot exceed date of entry.</p> <p>N= Allow date to exceed today's date.</p>
32=Qty Input	<p>Y=Allow input of quantities in SC Maintenance</p> <p>N=Do not allow</p>
34=Print Payment Date	<p>Y=Print payment date on payment authority.</p> <p>N=Do not print payment date.</p>
35=Retention Print on SC Payment Authorities	<p>Print Retention % and max retention and Bank Guarantee</p> <p>If set to 'Y', print both Max retention and Bank Guarantee amount</p> <p>If set to 'N' or blank, do not print max retention/bank guarantee</p> <p>If set to 'R', print max retention only</p> <p>If set to 'B', print Bank guarantee amount only</p>
36=Enable SC Rating in Payment Authorisation	<p>Y=Display a numeric rating value when authorizing payment</p> <p>N=Do not show</p>

GL Validation Parameters

These parameters are similar to Generic parameters, in that a three character prefix is added to a value to obtain the actual parameter code - in this case though, the value is used rather than the Work ID. The value can be from 1 to 3 alphanumeric characters.

These parameters can be maintained by selecting > *System Administration* > *Define Companies* > *Maintain Parameter* from the Jobpac main menu.

Profit Centre

When validating the three character code for General Ledger profit centre, the code is combined with "CTR" to form the parameter code. If the parameter is found, the thirty character profit centre description is returned. These parameters are required only if entries are to be made in the profit centre field in the GL Chart of Accounts Maintenance program.

CTRxx - Profit Centre

Account Group

When validating the three character code for General Ledger account group, the code is combined with "GRP" to form the parameter code. If the parameter is found, the thirty character account group description is returned. These parameters are required only if entries are to be made in the account group field in the GL Chart of Accounts Maintenance program.

GRPxx - Account Group

Record Type

When validating the one character code for General Ledger record type, the code is combined with "RTY" to form the parameter code. If the parameter is found, the thirty character record type description is returned. These parameters are required only if entries are to be made in the record type field in the GL Chart of Accounts Maintenance program.

RTYx - Record Type

System Parameter Reports

There are several system parameter listing reports available for use. This help for internal audit documentation.

List System Parameters

This provides a listing of the major system parameters and their values, if entered.

To access the List of System Parameters Report select > *System Administration* > *Define Companies* > *Reports* > *List System Parameters* from the Jobpac main menu.

You can also select viewing preferences for the report. Select the required report option: Spool file or PDF. Click *OK* and you are prompted 'Do you wish to proceed?' Click *Yes* to proceed or *No* to cancel and the report displays

List PO Parameters

This provides a listing of Purchase Order parameters.

To access the List of PO Parameters Report select > *System Administration* > *Define Companies* > *Reports* > *List PO Parameters* from the Jobpac main menu.

You can also select viewing preferences for the report. Select the required report option: Spool file or PDF. Click *OK* and you are prompted 'Do you wish to proceed?' Click *Yes* to proceed or *No* to cancel and the report displays

List AP Parameters

This provides a listing of Accounts Payable parameters. Please note that not all parameters are listed.

To access the List of AP Parameters Report select > *System Administration* > *Define Companies* > *Reports* > *List AP Parameters* from the Jobpac main menu.

You can also select viewing preferences for the report. Select the required report option: Spool file or PDF. Click *OK* and you are prompted 'Do you wish to proceed?' Click *Yes* to proceed or *No* to cancel and the report displays

List SC Parameters

This provides a listing of Subcontract parameters. Please note that not all parameters are listed.

To access the List of SC Parameters Report select > *System Administration* > *Define Companies* > *Reports* > *List SC Parameters* from the Jobpac main menu.

You can also select viewing preferences for the report. Select the required report option: Spool file or PDF. Click *OK* and you are prompted 'Do you wish to proceed?' Click *Yes* to proceed or *No* to cancel and the report displays

List Workids

This provides a listing of all Workids.

To access the List of Workids Report select > *System Administration* > *Define Companies* > *Reports* > *List Workids* from the Jobpac main menu.

You can also select viewing preferences for the report. Select the required report option: Spool file or PDF. Click *OK* and you are prompted 'Do you wish to proceed?' Click *Yes* to proceed or *No* to cancel and the report displays

Copying

Copying BAS & GST Codes

The following steps must be followed when copying the BAS & GST codes, select

> System Administration > Define Companies > Copy BAS & GST Codes.

Enter the code of the Work ID that you want to copy the BAS & GST codes from. The BAS & GST codes will be copied to the Work ID that you are in when you perform the copy.

Copying Creditors

The following steps must be followed when copying Creditors, select

> System Administration > Define Companies > Copy Creditors

Enter the code of the Work ID that you want to copy the Creditors from. Enter the Creditor Range that you wish to copy and finally enter the workid that you wish to copy the creditors to.

User Security

Create a New User

To add a new user to Jobpac please follow the below steps.

Select > System Administration > Define Security > User Profiles.

Work with User Profiles

Enabled
 Disabled
 Deactivated
 Expired
 Not Expired
 All

User Id	Name	Status	Output Queue	Outq Library	Expired	SSO VP1
ALARIKO	Rikshitha Alagesan - Trimble	*DEACTIVATED	JISOUTQ	QGPL	*NO	N
ALNPETO	Peter Alnas	ENABLED	JISOUTQ	QGPL	*NO	N
ALSBRIO	Jobpac - Brian Alston	DEACTIVATED	JISOUTQ	QGPL	*NO	N
ALSBR11	Brian Alston - Jobpac CA login	DEACTIVATED	JISOUTQ	QGPL	*NO	N
ARIKSHO	Rikshitha A	DEACTIVATED	JISOUTQ	QGPL	*YES	N
BADLES0	Lesley Badelles	ENABLED	EMLSPLFNAY	JPNAYPGM	*NO	N
BEAGLESEC	Glenys Beaumont - No IASP	DEACTIVATED	JISOUTQ	QGPL	*NO	N
BEAGLE0	Glenys Beaumont	ENABLED	JISOUTQ	QGPL	*NO	N
BEAGLE1	Glenys Beaumont - sniffer dog	DEACTIVATED	JISOUTQ	QGPL	*NO	N
BOUDAMO	Jobpac - Damien Bourke	ENABLED	JISOUTQ	QGPL	*NO	N

You will select another standard user from the list that appears, right click and select **Copy**.

Create User Profile

User Profile:

Password:

Description:

Output Queue:
 Library:

You will need to enter a user profile, initial password and Text description which would normally be the user's name. The output queue and library should be left as is.

The userid will always start with the 3 letter acronym for your company. Set the password to something simple like Welcome123, and then choose expire password. The user will then have to change the password when they first log on.

Defining User Access to a Work ID

Jobpac contains access and security functionality that allows users of the system to access Work ID's and programs within the work ID's. System parameters can also define which jobs users have access to.

Select > Systems Admin > Define Security > Work ID access

For a New User,

Enter USERID of the user and select **OK**

If the user is to have access to all Workids and projects, check this box, otherwise leave it blank, and select **OK**

Enter the workid that the user will have access to, and then select one of the three options regarding Jobs and Locations

- 1 = All Jobs and All Locations
- 2 = Not all Jobs but All Locations
- 3 = Not all Jobs and Not All Locations

For an Existing User

Enter USERID and **OK**

User Access Maintenance

 ACTIONS
 OK
 BACK

User Id

Remove access for all Work ID's

Check the **Remove Access for all Work ID's** check box, if required. Deleting access to all Work-IDs will enable a complete refresh of the user's security.

Otherwise just select OK, and the users current access is displayed, and can be added to

Note: The screen will appear with the details of the Work ID access already granted for the user. Enter the Work ID to be added and decide whether to give access to all jobs in the Work ID. To remove access to all jobs, the Work ID must be deleted and re-entered with Access to all Jobs column left blank.

Defining Job Security within a Work ID

The following steps must be followed to give a user access to jobs within the new Work ID if the user has not been given access to all jobs within a Work-ID. See below for an example.

Select > **System Admin > Define Security > Define Job Access by User**

Enter the name of the user and select **OK**

Job Security Maintenance By User ID

 ACTIONS
 OK
 BACK

User Id

< > ...

Job	Name ()	✎
TR01	Saman's Project	
TR02	Mithun's Project	
TR03	Odessa Mogol Project	
TR04	LesleyB Project	
TR05	Peter Alnas Project	
TR06	Teck's Project	
TR07	Ridhwaan M Project	
TR08	Training Project No 8	
TR09	Training Project No 9	
TR10	Shaneel Project	

< > ...

Job to be added

Skip to Job

Enter the details of the job to be added and select **OK**

You may also give access by Job.

Select > **System Administration > Define Security > Job Access by Job.**

Job Security Maintenance by Job

Job: TR91 Demonstration Project

ACTIONS OK BACK

< > ...

User	Level	
AITJACO	1	
ALNPETO	1	
ALSBRIO	1	
BADLESO	1	
BEAGLEO	1	
BOUDAMO	1	
BOUDAM2	1	
CADPHIO	1	
CALDODO	1	
CHEAMA0	1	

1 - Access to all jobs in all work ids
 2 - Access to all jobs in this work id
 3 - Access to this job in this work id

If cost centre security is on :

4 - Access to all cost centres for this job
 5 - Access to some cost centres for this job
 (You may only modify CC security for users with access level 5)

< > ...

User to be added

| 🔍

Add the USERID of the person to have access to this job

You may then ► *User to be added* to allow the user access to this job.

Enrol Users in CMS (Customizable Menu System)

Each user must have a menu structure in place to use Jobpac.

A separate Function Guide has been prepared for giving users a menu, and describing how to customise menus.

General Ledger Access

If General Ledger Security is in place, parameter GLASEC = Y, then you will need to maintain which GL accounts a user is able to view and transaction to.

To select General Ledger Access

> **System Administration > Define Security > General Ledger Access.**

G/L Account Security Maintenance

ACTIONS OK BACK

User Id: BOUDAM2 🔍

Work Id: 920 🔍 **TEST** DMB Sydney

Allow Access to all G/L Accounts?

You need to enter the user profile and the workid that you wish to either add or maintain this user's access to.

You can **Allow access to all General Ledger Accounts** by checking the box indicated and confirming this. If you do not want this user to have access to all General Ledger accounts select enter or *OK* to continue.

G/L Account Security Maintenance ACTIONS OK BACK

User Id BOUDAM2

< >

List Of Accounts User Has Access To

Delete Range
Delete Range
Delete Range
Delete Range
Delete Range
Delete Range

Please enter range of account numbers the user is authorised to access

Enter in format ***** (including the spaces)

From

To

If you do not allow access to all accounts then you will be able to enter a range of accounts that are permitted. Note that '*' is a wildcard.

You may enter multiple ranges.

G/L Account Security Maintenance ACTIONS OK BACK

User Id BOUDAM2

< >

List Of Accounts User Has Access To

Delete Range	From 100012000 To 1000510009
Delete Range	From 10007000 To 1000799999
Delete Range	
Delete Range	
Delete Range	
Delete Range	

Please enter range of account numbers the user is authorised to access

Enter in format ***** (including the spaces)

From

To

List Jobpac Access

You may need to review the access to jobs periodically to bring the access into line with corporate requirements.

To access this List of Jobpac Access select

> **System Administration > Define Security>List Jobpac Access**

Payroll Security

Payroll Security Levels

You can set up different payroll security levels so that you are able to control the users who have access to the employee master files. This enables you to safely control payroll runs between, say, wages and salaried employees as an example. Each employee would then have a security level on their master file. To enable this function, ensure that parameter PAYSEC has been set up and set to (Y)es

Select > **System Administration > Define Security > Payroll Security Levels.**

Payroll Security Level Maintenance			
Security Level	Description	Enquiry Level	
1	SALARIED	E	
2	WAGES	D	
3	QLD STAFF	D	

Valid security levels are as follows.

Code	Description
E = Executive	This is the highest level of access. It includes Salaried employees as well as Wages employees
D=Detail	This will allow access only to employee records set up as Permanent (Wages) and Temporary.
S=Summary	This will allow access only at summary level

On the employee master file, each employee needs one of these security codes.

Employee Maintenance - Pay Details
ACTIONS OK BACK

Employee BOURKEDM
MODIFY

PAY DETAILS
PERSONAL DETAILS
EMPLOYEE CONDITIONS
UDF DETAILS
UDF DETAILS 2
QUALIFICATIONS

Surname Given Other Initials

Status Salaried Permanent Temporary Bonafide Contract Voluntary Agreement Non Bonafide Contract Terminated

If Contractor, Enter Creditor Code to Create AP RCTI

Pay Period Weekly Fortnightly Monthly

RDO Code (Blank=None) RDO Credit ETS Config Code

Superannuation Rate %

Industry Super (Blank=None) Rates

Eligible for Leave Loading Rate %

Payment Method Bank Deposit Cash Cheque

Bank Branch Account

BSB Number Bank Account Title

Include Next Pay Run Standard Period Hours Rate Manual Rate Entry

Salary Hours Next Pay Normal Days/Week

Annual Salary Normal Hours/Day

Weekly Salary Last Pay Date

Normal Rate Time & Half Double Time Double & Half

Pay Rates

Tax Scale Tax File Number Declaration Provided Declaration Signed Date

Rebates-Dependant Calculate Tax T.F.N

HELP/SFSS? None Tax Free Threshold No Tax Free Threshold Zone

Australian Resident Seniors Offset Security Code Tax Free Threshold Claimed Home Loan

Send to ATO?

Grant Payroll Access

Once Payroll Security Levels have been put in place, you will need to setup user payroll security levels.

Select > **System Administration** > **Define Security** > **Grant Payroll Access**.

User Profile Maintenance
ACTIONS OK BACK

User Id

+ < > ...

Security Code	Description	Enquiry Level	
1	SALARIED	E	

Enter the user profile and then select **Add** from the **Actions** menu.

User Profile Maintenance ⏴ ACTIONS ✔ OK ⏮ BACK

User Id

+ < > ⋮

Security Code	Description	Enquiry Level	
1	SALARIED	E	
2	WAGES	D	

Scan Security Codes ✕

< > ⋮

Security Code	Description	Enquiry Level	
01	SALARIED	E	
02	WAGES	D	
03	QLD STAFF	D	
00			
00			

At any point in time to remove the user access right click on the security code in question and **Delete**.

Central Security

Central Security Access

Jobpac also has the ability to control a user’s access to a predetermined set of Jobpac programs from one central location. The programs control such areas as maintaining a user’s access to Work-IDs, Purchase Order Authorisation Value limits and Granting Payroll Access. At least one user is set up as a security user and this user has the ability to grant program access to other users or to remove program access from other users.

To use Centralised Security access, select

> System Administration > Define Security > Central Security Access.

User	User Name	User Id Active/Disabled	Central Security Access
ALARIKO	Rikshitha Alagesan - Trimble	A	N
ALNPETO	Peter Alnas	A	N
ALSBRIO	Jobpac - Brian Alston	A	N
ALSBRI1	Brian Alston - Jobpac CA login	A	N
ARIKSHO	Rikshita A	A	N
BADLESO	Lesley Badelles		N
BEAGLESEC	Glenys Beaumont - N		N
BEAGLEO	Glenys Beaumont	A	N

Right click on the user you wish to **Provide Central Security Access** to, or that you wish to **Remove Central Security Access** from.

Function - Allow Maintenance

- Work Id Access
- Menu Access
- Job Security
- Location Security
- G/L Account Security
- W/O Approval Levels
- PO Value Authorisation
- PO Job Authorisation
- Invoice Authorisation Limits
- Subcontract Approval Limits
- BFM User Access
- E-TS User Maintenance
- Grant Payroll Access
- Job Maintenance Access
- Budget Transfer Access

Any or all of these can be selected to allow that user to give that access to other users.

System Administration

Access Management

A user who has been set up with Central Security Access can be given permission to Add/Change and Delete access for other users in the functions that they have been permitted to control. For example, a user may be given permission to grant Add/Change Work-Id access for users but not be given permission to remove a user's access to the Work-ID Access program.

Select > **System Administration** > **Define Security** > **Access Management**

User Central Access Maintenance

Hide Apply

From: [] Contains [] = []

To: []

User	User Name	User Id Active/Disabled	
ALARIKO	Rikshitha Alagesan - Trimble	A	
ALNPETO	Peter Alnas	A	
ALSBRIO	John ...	A	
ALSBR11	Brian Austin - Jobpac CA login	A	
ARIKSHO	Rikshita A	A	
BADLESO	Lesley Badelles	A	
BEAGLESEC	Glenys Beaumont - No IASP	A	
BEAGLE0	Glenys Beaumont	A	
BEAGLE1	Glenys Beaumont - sniffer dog	D	

You can then select, for each program that the user has been given permission to control, whether that are allowed to Add/Change the access and whether they are allowed to Delete access to the program. Tick the boxes as appropriate.

User Access Maintenance

Beagle0 Glenys Beaumont Status Active

Function	Current Access	Add/Change Access	Delete Access
Work Id Access	<input checked="" type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Menu Access	<input checked="" type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Job Security	<input checked="" type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Location Security	<input checked="" type="checkbox"/>	<input type="checkbox"/>	<input checked="" type="checkbox"/>
G/L Account Security	<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>
W/O Approval Levels	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
PO Value Authorisation	<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>
PO Job Authorisation	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Invoice Authorisation Limits	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Subcontract Approval Limits	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
BFM User Access	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
E-TS User Maintenance	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Grant Payroll Access	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Job Maintenance Access	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Budget Transfer Access	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>

ACTIONS: Refresh, Add/Change Access, Delete Access, Delete All Access

Then select Add/Change Access from the Actions Menu. This will take the user successively through each of the individual security setup screens that have been ticked.

Job Setup Access

Jobpac allows a user to control any user's ability to add jobs and to modify data in the Job Setup program.

Select > **System Administration** > **Define Security** > **Job Setup Access.**

Maintain Jobs : Security																	ACTIONS	OK	BACK							
Hide Apply																	+	<	>	...						
From	Contains															From	=	=	=	=	=	=	=	=	=	From
To																To										To
User Id	Name	Wkid	Add	Type	Set	Val	SCH	INS	Cli	Sta	Guar	PD1	PD2	CMG	UDF	Base On User										
ALNPETO	Peter Alnas - Jobpac		Y	Y	Y	Y	Y	Y	Y	Y	Y	N	N			SADSHEO										
BADLES0	Lesley Badelles - Vi		Y	Y	Y	Y	Y	Y	Y	Y	Y	N	N													
BOUDAMO	Damien Bourke 0		Y	Y	Y	Y	Y	Y	Y	Y	Y	N	N													
KASSAM0	Saman Kashanchi- Job		Y	Y	Y	Y	Y	Y	Y	Y	Y	N	N			SADSHEO										
MAURID0	Ridhwaan Maudarun		Y	Y	Y	Y	Y	Y	Y	Y	Y	N	N													
MISSHA0	Shaneel Mishra - Job		Y	Y	Y	Y	Y	Y	Y	Y	Y	N	N			SADSHEO										
MOGODE0	Odessa Mogol		Y	Y	Y	Y	Y	Y	Y	Y	Y	N	N													
NARMIT0	Mithun Narayanan- Jo		Y	Y	Y	Y	Y	Y	Y	Y	Y	N	N			SADSHEO										
SADSHE0	Sheraz Sadik - Jobpa		Y	Y	Y	Y	Y	Y	Y	Y	Y	N	N													
TEOTECO	Teck Teo		Y	Y	Y	Y	Y	Y	Y	Y	Y	N	N													

Field	Description
User Id	User Profile as defined above
Name	This will be extracted from the user's name as enrolled in the CMS Menu
Work Id	Enter the Work-id if required or leave blank for all Work-Ids
Add	Y allows the user to add a new job. The option to Add a New Job will not appear unless the user has been given permission to Add. (Blank defaults to "N" – cannot add jobs)
Type	Y allows the user to edit information that appears in the Type tab. A user will not be able to edit fields in the Type tab unless the user has been given permission to do so. (Blank defaults to "N" – cannot edit)
Set	Y allows the user to edit information that appears in the Settings tab. A user will not be able to edit fields in the Settings tab unless the user has been given permission to do so. (Blank defaults to "N" – cannot edit)
Val	Y allows the user to edit information that appears in the Valuations tab. A user will be able to edit fields in the Valuations tab unless the user has not been given permission to do so. (Blank defaults to "Y" – can edit)
Sch	Y allows the user to edit information that appears in the Schedule tab. A user will be able to edit fields in the Valuations tab unless the user has not been given permission to do so. (Blank defaults to "Y" – can edit)
Ins	Y allows the user to edit information that appears in the Insurance tab. A user will be able to edit fields in the Insurance tab unless the user has not been given permission to do so. (Blank defaults to "Y" – can edit)
Cli	Y allows the user to edit information that appears in the Client tab. A user will be able to edit fields in the Client tab unless the user has not been given permission to do so. (Blank defaults to "Y" – can edit)
Sta	Y allows the user to edit information that appears in the Staff tab. A user will be able to edit fields in the Staff tab unless the user has not been given permission to do so. (Blank defaults to "Y" – can edit)

Field	Description
Guar	Y allows the user to edit information that appears in the Guarantees tab. A user will be able to edit fields in the Guarantees tab unless the user has not been given permission to do so. (Blank defaults to “Y” – can edit)
PD1	Y allows the user to edit information that appears in the Property Development tab 1. A user will be able to edit fields in the Property Development tab 1 unless the user has not been given permission to do so. (Blank defaults to “Y” – can edit)
PD2	Y allows the user to edit information that appears in the Property Development tab 2. A user will be able to edit fields in the Property Development tab 2 unless the user has not been given permission to do so. (Blank defaults to “Y” – can edit)
CMG	Y allows the user to edit information that appears in the Construction Management tab. A user will not be able to edit fields in the Construction Management tab unless the user has been given permission to do so. (Blank defaults to “N” – cannot edit)
UDF	Y allows the user to edit information that appears in the UDF tab. (Blank defaults to “Y” – can edit) Note, this tab will only be available if the Job User definable fields parameter has been set on and the fields defined.
Base on User	Enter a user profile that can be copied to set up a new user’s profile. Note that if a change is made to the original user’s profile, the changes will not be copied to the any other user. However you can use the Base on User Profile field to filter the users that are displayed to make it more efficient to make bulk changes.

Maintain Budget Approvals

It is possible to control who can approve budget transfers within the Budget Transfers program. If parameter BUDFXR Budget Transfer Approvals is set to seek approval for requests for budget transfers then it is necessary to establish a table of approvers and set up the category of transfer that each user is permitted to approve. This can be done for Internal Contingency, Internal Provision for Rise and Fall, Contract Margin, Undistributed Budget and Budget Transfer Between Cost Centres.

Select > **System Administration > Define Security > Maintain Budget Approvals**

User Id	Name	Wkid	All Jobs	Budget Transfer Type Internal Contingency	Budget Transfer Type Internal Prov Rise and Fall	Budget Transfer Type Contract Margin	Budget Transfer Type Undistributed Budget	Budget Transfer Type Cost Centre Transfer
BOUDAMO	Damien Bourke 0	920	Y	Y	Y		Y	Y

You can then select, for each user and Work-Id, what the user has permission to approve in the categories defined. For example in one Work-Id a user may be permitted to approve the transfer

of values between all of the categories and another user may be permitted only to approve only some transfers. You can also restrict the transfers to permitted jobs.

If the user has access only to some jobs then you can right click on the user and select the jobs to which the user has approval authority. For example, you can select some categories for one or more jobs.

Maintain Budget Transfer Approvals - Jobs

 ACTIONS
 OK
 BACK

User BOUDAM0 Damien Bourke 0
 Work Id 920 **TEST** DMB Sydney

Hide
 Apply

From = = = =

To

Job	Job Name	Budget Transfer Type Internal Contingency	Budget Transfer Type Internal Prov R&f	Budget Transfer Type Contract Margin	Budget Transfer Type Undistributed Budget	Budget Transfer Type Cost Centre Transfer
2180	Large Park	Y	Y		Y	Y


Design Menu

Users of Jobpac will require different functions to be able to complete their roles within your organization. For a number of reasons such as security of data, you will want to ensure that user's access to Jobpac functions is organised efficiently and you will want to restrict access to other areas within Jobpac by user. This can be done using a menu structure.


There is a separate Function Guide that explains how to create and modify menus

Maintain CMS User Message

You are able to maintain the message that appears on the Jobpac screen under heading Broadcast.




This is done via > **System Administration > Define Menus > Maintain CMS User Message.**



List Current CMS Users

Select via path > **System Administration > Define Menus > List Current CMS Users.**

This function displays the users currently active in Jobpac and shows the function that they are running. Options to display their job information or send them a message are included to facilitate enquiry and analysis of current tasks by the system administrator. It is a quick way of telling if a user is running a particular program or checking if any users are logged into AP transaction entry before doing a payment run for example.



Display Active Licence Users

This option displays the number of licence users active on the system at the time. This can be used to check if users have not logged off correctly and are using licenses that could be made available to others. This is available via path

> **System Administration > Define Menus > Display Active Lic Users.**

The screenshot shows a window titled "Display Active License Users" with a close button (X) in the top right corner. The window is divided into two main sections. The top section is a summary table with columns for License Type, Licensed, and Active. The bottom section is a detailed table with columns for No., IP Address, User Id, User Name, Workstation Id, Full Lic, Partial Lic, PM User, Field User, and FV Use.

License Type	*NAMED	Licensed	Active
Full Licenses		100	1
Partial Licenses			
Project Management Licenses		2	
Field Licenses		3	
Field View Licenses		4	

No.	IP Address	User Id	User Name	Workstation Id	Full Lic	Partial Lic	PM User	Field User	FV Use
1	10.128.13.199	STGVPID01	VPID TestUser	QPADEV0008	Y	N	N	N	N

Database Integrity

There are a number of functions here to assist with maintaining the integrity of Jobpac data and data relationships. Some of these utilities are for use only by Jobpac consultants and may not be displayed on the menu.

These programs would always be run under the direction of the Viewpoint Support Team or as instructed by your Jobpac consultant.

Database Integrity Checks

This function allows the check of the validity of various sub-totals, totals and summary values. Not all values are available for checking.

Select the library on which the check is to be run by entering a Y in the Rebuild (Y/N) column and click on Done in the box below.

Check for GL Batches Out of Balance

This function allows you to check for imbalances in the GL details. It submits a report and does not have a display.

The report is a list of batches that are out of balance, which may be the cause of a Trial Balance error. Please note that some very long payment runs may create two batches that balance when combined.

Rebuild GL Summary Only

This function rebuilds the GL Summary values from the GL details. It submits a report and does not have a display.

This is for use by Viewpoint staff only.

3 Way Cost of WIP Comparison Report

This program is used to identify any differences between the CWIP Enquiry, CWIP Report, and the Cost Comparison and Forecast Report. The report can be run for a job, or a Work-Id, for a range of periods, or project to date.

Set Integrity Level

This program set the level used in the Database Integrity Checks program. Check with your Jobpac consultant or the Jobpac Service Desk before changing any of the pre-set values.

Utilities

There are a number of functions here to assist with resolution of user issues. Some of these utilities are for use only by Jobpac consultants and may not be displayed on the menu.

Unvoid a Cheque

This function allows you to unvoid a cheque.

To do this **select > System Administration > Utilities > Unvoid a Cheque**

A screen is presented that allows a selection of cheques that have been marked as void, but need to be returned to a non-voided status.

Field	Description
GL Bank Account	Enter the GL bank account on which the voided cheques were drawn
From Cheque No	Enter the starting cheque number to unvoid
To Cheque Number	Enter the finish cheque number.

Reset a Payment Run

Only one person at a time can be doing the following

- EFT Consolidation
- Cancel EFT
- Cancel Cheque
- AP Payment Run

If a second person tries, they get an error message

If this has happened because the person has left without closing down the EFT consolidation screen, then this function allows you to reset the lock flag.

To do this select >

System Administration > Utilities > Clear EFT consolidation/Cancel EFT/AP Payrun

EFT Cons / Canc, Payrun Lock Notice

 ACTIONS OK BACK

BOUDAMO has locked EFT Consolidation at 13:18:25 on 19/04/20
Do you want to clear the lock?

Selection does not trigger any response but the system clears the lock.

Reset Subcontract

This function allows you to release a subcontract agreement that is locked. To do this select >
System Administration > Utilities > Reset Subcontract

Unlock S/C Agreements

 ACTIONS OK BACK

User *ALLUSERS

All of the agreements listed below are locked by you. If you are using an agreement in another Jobpac session, you should return that session to a menu. If not, your Jobpac session may have dropped out when you were last in the agreement.

Hide Apply

User	Agreement Number	Description	Creditor	Job	Edit
TEOTECO	TR069001	Drainage System	ABELPIPE	TR06	⋮

Right click on the agreement and **Unlock** to release the agreement.

Set Cost Centres To

This function allows you to modify all cost centres for a Cost Plus job to match the setting on the Job. To do this select >

System Administration > Utilities > Set Cost Centres To.

Update Miscellaneous Job Values

 ACTIONS OK BACK

Job
 Cost Plus Job

Values to update -

Cost Plus Job : Y
 Markup % : 10.00
 Flag cost centres not already marked / unmarked as Cost Plus with values from Job
 Flag existing cost centres already marked as Cost Plus with values from Job

Tick the required options, and select the **Update** option

Update Miscellaneous Job Values

 ACTIONS OK BACK

Job
 Cost Plus Job

Values to update -

Cost Plus Job : Y
 Markup % : 10.00
 Flag cost centres not already marked / unmarked as Cost Plus with values from Job
 Flag existing cost centres already marked as Cost Plus with values from Job

ACTIONS
 OK BACK

Prompt
Refresh
Update

Clear EFT Consolidation/EFT Cancellation/Payment Run

If any user drops out of the system while using one of:

- EFT Consolidation
- EFT Cancellation
- AP Payment Run
-

This can be used to reset the 'In Use' flag.

Validate Email Addresses

This option can be used to validate email addresses used by the JOM FORMS module, i.e. eContact Maintenance, Employee Maintenance, Creditor Maintenance.

The checks are:

- a. Can't be blank
- b. Must start with a letter or number
- c. Must consist of only letters, numbers, @, _, and .
- d. Must have at least one .
- e. . can't be last character
- f. Must have only letters to the right of the last .
- g. Must have an @
- h. Must have ONLY one @
- i. @ can't be last character
- j. Must have only a letter or a number immediately left and right of @

A report of errors is produced.

Unfinalise Budget

This function DELETES all budget transfers, including the audit trail, and resets the original budget to the current budget.

It cannot be run if transferred variations exist.

Select > System Administration > Utilities > Unfinalise budget.

Unfinalise Budget for Job ⌵ ACTIONS ✔ OK ➔ BACK

Job

Note : This is a very powerful function. It should only be run by your Jobpac consultant.
It deletes all budget transfers, including audits, and resets the original budget to the current budget.

Change a Subcontract Value

This function allows you to change a lump sum subcontract budget value after finalisation.

To do this select > **System Administration > Utilities > Change Subcontract Value**

To change agreement values enter a valid agreement number and note that this only applies to Lump Sum subcontracts. Press OK to continue.

Select the subcontract item you want my highlighting the line in the list, right clicking and selecting Select or by double clicking the line item.

Changes are made on the bottom line

▶ ACTIONS
 ✔ OK
 ⏪ BACK

Job: TR91 Demonstration Project
 Subcontractor: ABELPIPE
 Agreement Number: TR919001 Drainage System LUMP SUM

Nett Contract Sum 52,000.00

Item	Description	Cost Code	CT	Cost Centre Description	Amount	Budget \$	Bud. %	
1	Main Line	0223	SC		8,060.00	12,060.00	18.84	
2	Drainage System	0223	SC		8,320.00	8,320.00	13.87	
3	Dripline	0223	SC		17,160.00	17,160.00	28.60	
4	Water Connection to various	0223	SC		2,080.00	2,080.00	3.47	
5	Control Valves	0223	SC		8,840.00	8,840.00	14.73	
6	Control system	0223	SC		7,280.00	7,280.00	12.13	
7	Cabling	0223	SC		260.00	260.00	0.43	

1 Main Line
 0223
 SC
 Subbie - Plumbing
 8,060.00
 12,060.00
 18.84

Field	Description
Amount	Enter a budget value for the subcontract item.
Budget \$	Enter a value for the total amount of committed budget you wish to allocate.
Budget %	Represents the Budget \$ allocated as a percentage of total current budget for the cost centre.

Click *OK* to save your data.

Bulk Cost Centre Delete

This function allows you to delete cost centres on a job in bulk, provided that the following criteria are met

- No original budget
- No Current budget
- No budget adjustments (transfers, variation, qty changes)
- No outstanding costs
- No actual costs
- No FCC
- No FFC
- No Job Journals
- No worksheet lines
- No Cost Centre Revenue

To do this select > System Administration > Utilities > Bulk Cost Centre Delete

Configure Modules

There are a number of configurable options in each module for Jobpac; you are able to use these to fit Jobpac to your business.


Accounts Receivable

Follow-Up Actions


To assist debt collection, you are able to setup a number of follow up actions that can be recorded against the debtor or the outstanding invoice, so that all users who can access Accounts Receivable are able to review the status of any outstanding debt.

This is setup under

> System Administration > Configure Modules > Accounts Receivable > Follow-Up Actions.



The code has an associated description which can be used to provide more details of the action.



Job Costing

Job Types

Job Types help describe different job characteristics that you are then able to report on. A number of reports have a filter by Job Type, for example the Project Summary Report. These are not used for determining how a project processes transactions. They are for filtering and reporting purposes only.

This is available under

> System Administration > Configure Modules > Job Costing > Job Types.

To add a new job type, simply enter it at the bottom of the screen. To delete a job type right click and **Delete**.

Resource Code Master List

This is available under >

System Administration > Configure Modules > Job Costing > Resource Master Cost List.

This function defines the master schedule of available resource codes to use within Jobcosting if a job has resource code level costing enabled as both system and job parameters. The use of resource codes allows for the capture and reporting of costs at a level additional to that of cost centre.

Code	Description	Status	Type	CT01	CT02	CT03	CT04	CT05	CT06	CT07	CT08	CT09	CT10
32MPA	32MPA Concrete Mix	A											
3300	Supply - Sand & Aggregates	A											
3330	Supply - Geotextiles/Ver Drns	A											
3400	Supply - Piping Materials	A											
3600	Supply - Reinforcement	A											
3650	Supply - Cement/Lime	A											
3652	Supply - Concrete Readymixed	A											
3655	Supply - Shotcrete	A											
3656	Supply-Shotcrete Accelerator	A											
3660	Supply - Precast Concrete	A											

To modify a resource code you may select a line and modify the existing data or to add a new Resource Code position to the end of the list via the Page Down key.

Field	Description
Code	When adding, enter up to ten characters to define a Resource Code
Description	Enter text to further describe the Resource Code
Status	(A)ctive or (C)losed
CT01 – CT10	A list of cost types for which entry of this resource code is valid .i.e. a resource code may only be valid when costing to, say, Plant and Equipment cost types. If left blank then all cost types are allowable for entry.

If you need to Cost Type Define Constraints then highlighting the line in the list, right clicking and selecting Select or by double clicking the line item will display a list box as shown below.

Resource Code Maintenance

Default Resource Code

ACTIONS OK BACK

XLS < > ...

Code	Description	Status	Type	CT01	CT02	CT03	CT04	CT05	CT06	CT07	CT08	CT09	CT10
32MPA	32MPA Concrete Mix	A											
3300	Supply - Sand & Aggregates	A											
3330	Supply - Geotextiles/Ver Drns	A											
3400	Supply - Piping Materials	A											
3600	Supply - Reinforcement												
3650	Supply - Cement/Lime												
3652	Supply - Concrete Readymixed												
3655	Supply - Shotcrete												
3656	Supply-Shotcrete Accelerator												
3660	Supply - Precast Concrete												
3800	Supply - Structural Steelwork												
3830	Supply - RockAnchors/Bolts												
3990	Supply - Misc Perm Materials												
4000	Miscellaneous Temp Materials												
4001	Residual on Temporary Material												
4100	Formwork & Falsework Material												
4140	Formwork Systems												

Constraints

Resource Class 32MPA

LW (Wages)

LS (Salaries)

MP (Perm.Matrl)

MT (Temp.Matrl)

MS (Oth.Matrl)

PI (Plant-Int.)

PE (Plant-Ext.)

ST (Trade S/C)

SN (Nom. S/C)

SH (Hire S/C)

RESCCONST01

OK Close

Assign Work Order Approval Levels

Users are required to be assigned work order approval levels if the Jobpac Service Order module is in use. This function allows a maximum approval value in dollars to be assigned to a user profile.

This is available under

> **System Administration > Configure Modules > Job Costing > Assign W/Ord Approvl Lvl.**

Service System - Maintain User Maximum Authorisation Values

ACTIONS OK BACK

Hide Apply XLS + < > ...

From Contains From

To To

User	Name	Maximum Authorisation Value
BOUDAMO	Damien Bourke	100,000.00
KWOOHSO	Oh Soo Kwon	1,000,000.00
STGFENORO	Norm Feile	1,000,000.00
TANHANO	HP Tan	888,888.88
WALGARO	Gary Walsh	2,000,000.00

Maintain Departments

To setup departments as required for Service Orders. These are similar to Job Groups, and a separate set of GL accounts can be assigned to different Departments. This is available under

> **System Administration > Configure Modules > Job Costing > Maintain Departments.**

You can Select an existing department to edit the details, Copy the details to a new department or delete an existing department.

To add a new Department, click on the Add function on the sidebar.

Service System - Department Maintenance

 ACTIONS
 OK
 BACK

Cost G/L Control Account for cost types

< > ...

CT	Description	Account	Description
LW	Wages	2B5102	MOS REVENUE
LS	Salaries	2B5102	MOS REVENUE
MP	Perm.Matrl	2B5102	MOS REVENUE
MT	Temp.Matrl	2B5102	MOS REVENUE
MS	Oth.Matrl	2B5102	MOS REVENUE
PI	Plant-Int.	2B5102	MOS REVENUE
PE	Plant-Ext.	2B5102	MOS REVENUE
ST	Trade S/C	2B5102	MOS REVENUE
SN	Nom. S/C	2B5102	MOS REVENUE
SH	Hire S/C	2B5102	MOS REVENUE

Valid fields are as follows.

Field	Description
Department	A ten character Department key.
Description	Enter text to further describe the Department
Manager	The name of the departmental manager
Revenue GL Control Account	The GL account to which Certified progress claims and Sundry Invoices are credited for jobs assigned to this type.
Control Accounts for Cost Types	A list of cost types and the GL account to which costs are to be posted for this cost type.

Define Schedule Intervals

This is available under > *System Administration* > *Configure Modules* > *Job Costing* > *Define Schedule Intervals*.

Service interval maintenance is used in conjunction with the Service Order Module and allows the definition of user specified intervals and descriptions.

Service System - Schedule Interval Maintenance						
Interval	Description	Year/s	Month/s	Week/s	Day/s	
1D	Daily				1	
2W	Fortnightly			2		
1W	Weekly			1		
1M	Monthly		1			
3M	Quarterly		3			
6M	Half yearly		6			
1Y	Yearly	1				

To maintain the schedule intervals simply enter or overtype the appropriate fields.

Register Type Maintenance

This is available under

> System Administration > Configure Modules > Job Costing > Register Type Maintenance.

Register Types are used to define and categorise bulk material type registers such as Concrete, Steel etc. and can be used in conjunction with Product Codes where a product is linked to a register type, or independently of them.

Maintain Register Types			
Register Type	Description	Default	
CONCRETE	Concrete Register	Yes	
QUARRY	Quarry Products	No	
REO	Reinforced Steel Register	No	

You can also **Delivery Docket User Fields** which allows the definition of user definable field values that are captured when using the Bulk Materials Register Breakdown (BMR) facility that's available through an alternate version of Delivery Docket Entry where deliveries are captured by Job, Register Type and Supplier code rather than through Purchase Order Items.

Maintain Register Types			
Register Type	Description	Default	
CONCRETE	Concrete Register	Yes	
QUARRY	Quarry Products	No	
REO	Reinforced Steel Register	No	

- Set As Default
- Delivery Docket User Fields
- Delivery Docket Entry Fields
- Delete
- Prompt

System Administration

Setup Bank Guarantee Status

You are able to maintain bank guarantees in Jobpac and they are required to have a status as to where they are at in their cycle.

This is available under

> System Administration > Configure Modules > Job Costing > Setup BG Status.

Status	Description
C	Closed
O	Open
R	Review

To add a new bank guarantee status select ► *Add Status* from the *Sidebar* Menu. To delete right click and select ► *Delete*.

Reporting Units

Job Reporting Units help define different job characteristics that you are then able to report on.

This is available under

> System Administration > Configure Modules > Job Costing > Reporting Units.

Reporting Unit	Description
CS	Consulting Services
ES	Environmental Services
PS	Petrochemical Services
SS	Special Services

Reporting Sub Units

Job Reporting Sub Units help define different job characteristics that you are then able to report on.

This is available under

> System Administration > Configure Modules > Job Costing > Reporting Sub-Units.


Both Reporting Units and Sub-Reporting Units are subsidiary to Job Groups

Job Group Codes

To assist with more accurate reporting of job characteristics you are able to define group code, reporting unit and reporting sub unit relationships, so that users can define the job according to the same criteria. You can then assign Reporting Units and Reporting Subunits the Group Code to maintain consistency of reporting.

This is available under

> **System Administration > Configure Modules > Job Costing > Job Group Codes.**



To assign Reporting Units and Reporting Subunits the Group Code to right click, and select **RU's or SU's** and enter the Reporting Units and Reporting Subunits.


Set Retention Percentage Ranges

Jobpac is able to calculate retentions for both progress claims and for subcontractor claims. These retention rules need to be setup based upon contract conditions.

These are used only in New Zealand.

This is available under

> **System Administration > Configure Modules > Job Costing > Set Retn % Ranges.**



To add a new retention rule simply enter it on this screen. See Select for entry details

To modify an existing range you then need to define the retention calculation by right clicking on the rule and **Select**. Enter the percentage and the 'To amount'. Select OK after each line.

Retention Calculation Method Maintenance			
Retention %	From Amount	To Amount	
10.00		10,000	
6.00	10,000	60,000	
2.50	60,000	100,000,000	

Job User Definable Fields

If the parameter JOBUDF is set to “Y” then users can establish tables of values for users to select from when in Job Setup.

> **System Administration > Configure Modules > Job Costing > Job User Defined Fields.**

See separate Function Guide for User Defined Fields.

General Ledger

Consolidations Define Levels

Jobpac allows you to consolidate the financial results across workids. To do this you firstly need to define the consolidation level.

> **System Administration > Configure Modules > General Ledger > Define Levels.**

Consolidation Level Maintenance	
Level Id	Description
10	DMB GR
20	DMB SYD

You may add a new consolidation level by entering it at the bottom of the screen.

You may **Define Workids** that will make up this consolidation level. This allows you to assign one or more Work-Ids to a consolidation level.

Consolidation Level Maintenance - Define Workids						
Consolidation Level 10		DMB GROUP				
Wkid	Work Id Description	%equity	Exchange Rate	Col No.	Column Heading	
910	**TEST** DMB Holding Company	100.00	1.000000000			
920	**TEST** DMB Sydney	100.00	1.000000000			
930	**TEST** DMB Victoria	100.00	1.000000000			
940	**TEST** DMB Queensland	100.00	1.000000000			
950	**TEST** DMB ACT	100.00	1.000000000			
955	**TEST** DMB SA	100.00	1.000000000			
960	Training Workid 960	100.00	1.000000000			
970	Training Workid 970	100.00	1.000000000			

Simply enter the Work-id number and the Equity percentage to be included in the consolidation. The Exchange Rate is for Workids with a different Currency

The column number is no longer used.

You may also **Define Account Eliminations** upon consolidation.

Consolidation Level Maintenance - Define Acct Eliminations
ACTIONS OK BACK

Level Id 10 DMB GROUP

< > ...

From Wkid	From Account	From Description	To	To Account	To Description
920	20006011	Associated Revenue	930	30008099	Historic Costs - Offset

Consolidations Define Account Summaries

You must define the summaries you require when you run consolidated Trial Balance Report, P&L Report, and Balance Sheet Report.

This is available under

> System Administration > Configure Modules > General Ledger > Define Account Summaries.

Account Summary Definition Maintenance
ACTIONS OK BACK

Hide Apply

= Contains ----- * * = Wild card
(Enter Code only to delete)

Code	Description	Account Mask
1	Summary to Master Chart	****_***
2	Summary to Company	****_-----
3	All Accounts	-----

New Account Summaries are added in the top line.

Consolidations Apply Definitions

Once you have completed the above steps you must apply the definitions to create the consolidated files. This job can be scheduled.

> System Administration > Configure Modules > General Ledger > Apply Definitions.

Apply New Consolidation Definition
ACTIONS OK BACK

This process will apply the working consolidation definition and rebuild the consolidation data based on that definition.

Schedule the job

If yes, Enter Scheduled Date

Scheduled Time

Intercompany Control Parameters

Jobpac's Intercompany facility enables the automatic generation of GL transactions between loan accounts from one Work ID (source Work ID) that relates to other Work ID(s) (target Work ID) in other Work ID(s). Typical transactions for using intercompany accounting might be the reallocation of overhead expenses through journals or coding the cost allocation for an Accounts Payable invoice line item that relates to another work ID.

In order to be able to facilitate intercompany processing in Jobpac, the Intercompany Control Account (ICA) parameters must be setup. There are some rules that must be followed when setting up the relationship parameters:

- Work ID's must exist in the same database
- A separate record must be defined for each relationship. This involves defining relationships between Work ID's as both the target and the source
- G/L Intercompany Accounts must be established
-

Select > System Admin > Configure Modules > General Ledger > Control Parameters

⏏ ACTIONS
 ✔ OK
 ⏪ BACK

To select a GL account, use the Prompt menu or enter "?" and click OK

Hide Apply
 ⏪ ⏩ ⋮

From	Contains	From	From	Contains	From
<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>
<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>
Source Work Id	Source Description	Source I/C Account	Target Work Id	Target Description	Target I/C Account
910	**TEST** DMB Holding Company	10003020	920	**TEST** DMB Sydney	20003010
910	**TEST** DMB Holding Company	10003030	930	**TEST** DMB Victoria	30003010
910	**TEST** DMB Holding Company	10003040	940	**TEST** DMB Queensland	40003010
910	**TEST** DMB Holding Company	10003050	950	**TEST** DMB ACT	50003010
910	**TEST** DMB Holding Company	10003055	955	**TEST** DMB SA	55003010
910	**TEST** DMB Holding Company	10003056	960	Training Workid 960	60003010
910	**TEST** DMB Holding Company	10003057	970	Training Workid 970	70003010
920	**TEST** DMB Sydney	20003010	910	**TEST** DMB Holding Company	10003020
920	**TEST** DMB Sydney	20003030	930	**TEST** DMB Victoria	30003020
920	**TEST** DMB Sydney	20003040	940	**TEST** DMB Queensland	40003020
920	**TEST** DMB Sydney	20003050	950	**TEST** DMB ACT	50003020
920	**TEST** DMB Sydney	20003055	955	**TEST** DMB SA	55003020
920	**TEST** DMB Sydney	20003056	960	Training Workid 960	60003020
920	**TEST** DMB Sydney	20003057	970	Training Workid 970	70003020
930	**TEST** DMB Victoria	30003010	910	**TEST** DMB Holding Company	10003030
930	**TEST** DMB Victoria	30003020	920	**TEST** DMB Sydney	20003030
930	**TEST** DMB Victoria	30003040	940	**TEST** DMB Queensland	40003030
930	**TEST** DMB Victoria	30003050	950	**TEST** DMB ACT	50003030
930	**TEST** DMB Victoria	30003055	955	**TEST** DMB SA	55003030

You may also set up a Centralised Balance Sheet which can be configured to fit your organisation by selecting **Centralised BS Control** from the **Actions** menu.

Your Jobpac Consultant should be utilised to set this up.

Intercompany Balance Sheet Control Maintenance														ACTIONS	OK	BACK
To select a GL account, use the Prompt menu or enter "?" and click OK																
Wkid	Cent Crd/Dbt Wkid	Cent GST Post	Cent Oth A/C Post	Cent Bank	Allow I/C Cost	Trade Creditor	Trade Creditor Retention	Debtor Control	Trade Debtor Retention	S/C Control	S/C Retention Control	GST Input	GST Output	Accrual Account		
910	910	N	N	Y	Y	10003011	10003021	10001301	10001351	10003051	10003061	10003402	10003401	10001601		
920	910	N	N	Y	Y	20003011	20003021	20001301	20001351	20003051	20003061	20003402	20003401	20001601		
930	910	N	N	N	Y	30003011	30003021	30001301	30001351	30003051	30003061	30003402	30003401	30001601		
940	910	N	N	N	Y	40003011	40003021	40001301	40001351	40003051	40003061	40003402	40003401	40001601		
950	910	N	N	N	Y	50003011	50003021	50001301	50001351	50003051	50003061	50003402	50003401	50001601		
955	910	N	N	N	Y	55003011	55003061	55001301	55001351	55003051	55003061	55003402	55003401	55001601		
960	910	N	N	N	Y	60003011	60003061	60001301	60001351	60003051	60003061	60003402	60003401	60001601		
970	910	N	N	N	Y	70003011	70003061	70001301	70001351	70003051	70003061	70003402	70003401	70001601		

Field	Description
Crd/Dbt Work ID	The workid that you wish to use as the source for debtors and creditors.
GST Post	Y (yes) or N (no) if you wish to centralize the GST or leave it in each individual workid.
Other A/C Post	Y (yes) or N (no) if you wish to centralize the other account postings (such as Trade Debtors and Creditors) or leave it in each individual workid.
Bank	Y (yes) or N (no) if you wish to centralize the bank account or leave it in each individual workid.
Allow I/C Cost	Y (yes) or N (no) if you wish to allow cost transfers between workids.
Trade Creditor	GL control account this overrides the parameters, this may be either at centralized workid or the source workid
Trade Creditor Retention	GL control account this overrides the parameters, this may be either at centralized workid or the source workid
Debtor Control	GL control account this overrides the parameters, this may be either at centralized workid or the source workid
Trade Debtor Retention	GL control account this overrides the parameters, this may be either at centralized workid or the source workid
S/C Control	GL control account this overrides the parameters, this may be either at centralized workid or the source workid
S/C Retention Control	GL control account this overrides the parameters, this may be either at centralized workid or the source workid
GST Input	GL control account this overrides the parameters, this may be either at centralized workid or the source workid
GST Output	GL control account this overrides the parameters, this may be either at centralized workid or the source workid
Accrual Account	GL control account this overrides the parameters, this may be either at centralized workid or the source workid

Exchange Rate Maintenance

You are able to define exchange rates to be used in Purchase Orders, AP Invoices and Payments.

See separate Function Guide for Foreign Currency Setup in Jobpac.

> **System Administration > Configure Modules > General Ledger > Exchange Rate Maintenance.**

This initially shows as an empty screen as only active currencies display.

Currency	Description	Numeric Code	Sts	Dec Pos	High Symbol	High Name	Low Symbol	Low Name	

Remove the Filter for Status.

Currency	Description	Numeric Code	Sts	Dec Pos	High Symbol	High Name	Low Symbol	Low Name	
CLP	CHILE	152	I	0		Peso			
CNY	CHINA	156	I	2		Yuan Renmi		Fen	
COP	COLOMBIA	170	I	2		Peso		Centavo	
COU	COLOMBIA	970	I	2		Unidad de		?	
CRC	COSTA RICA	188	I	2		Colon		Centimo	
CUC	CUBA	931	I	2		Peso Conve		?	
CUP	CUBA	192	I	2		Peso		Centavo	

Then select the currency to setup the exchange rate.

Base Currency	AUD	AUSTRALIA
Currency	CNY	CHINA

Entry Date	Entry Time	Exchange Rate CNY To 1 AUD	Comments
19/04/2022	20:27:16	4.702900000	Rate from 1/4/2022

ETS & Billing

This is described in more detail in the ETS Time and Billing Manual.

Standard Text Maintenance

There is also the option of adding standard text to particular purchase orders where the standard text clause is linked by the system parameter PRSTXT. If this parameter is set then

System Administration

the standard text clause will be printed automatically, otherwise a standard text may be selected on an ad hoc basis when creating and printing purchase orders. It is added after the purchase items are listed.

This is available under

> System Administration > Configure Modules > Procurement & eInvoicing > Std Text Maintenance.

Enter a new code or select from a list of existing codes.

Text Code	Description
ARIN	SECURITY PAYMENT ACT
STD	STANDARD ORDER TEXT

Maintain Value Limits

These option refer to the 'Old' approval processes in Jobpac. They have been superseded by Advanced Approvals.

- Purchase Order Limits
- Invoice Authorisation Limits
- Subcontract Approval Limits

Document Set Maintenance

Please refer to the PVRS and Expediting Manuals for further instruction.

Location Security Maintenance


You are able to authorize invoices by either location or job. A user needs to have access to the location box in order to be able to review and ultimately approve invoices.

This is available under >

System Administration > Configure Modules > Procurement & eInvoicing > Location Security Maint.

Select the user profile you are wishing to maintain by using the scan facility.


You may then add text to the header code as shown below. .



The screenshot shows the 'Subcontract Heading Text Maintenance' interface. At the top, there are three buttons: 'ACTIONS' (down arrow), 'OK' (green checkmark), and 'BACK' (orange arrow). Below the header, there is a table with two columns: 'Code' and 'Description'. The first row contains 'STD' and 'Security payment act'. Below the table is a text input field containing the text: 'This is a payment claim made under the Building and Construction Industry Security of Payment Act 1999'.

To maintain Master Footer codes select Option 2. Process is the same as for Header Codes


To Maintain Reason Codes select Option 3. These are Standard Reason for Difference Codes used in SC Payments



The screenshot shows the 'Subcontract Standard Reason Code Maintenance' interface. At the top, there are three buttons: 'ACTIONS' (down arrow), 'OK' (green checkmark), and 'BACK' (orange arrow). Below the header, there are 'Hide' and 'Apply' buttons. To the right, there are navigation icons: a plus sign, left arrow, right arrow, and three dots. Below these are two input fields: 'From' and 'To', with a 'Contains' label between them. Below the input fields is a table with three columns: 'Code', 'Description', and an empty column. The first row contains 'NONCOMP' and 'Non Compliance to standards agreed'. The second row contains 'QTY' and 'QTY Claimed not verified'.

You may then add text to the header code as shown below.

The Reason Description is a short text field, partly limited by the need to fit the text into a narrow space on the subcontract documents.



The screenshot shows the 'S/C Standard Reason Description Maintenance' interface. At the top, there are three buttons: 'ACTIONS' (down arrow), 'OK' (green checkmark), and 'BACK' (orange arrow). Below the header, there is a table with three columns: 'Reason Code', 'Code', and 'Description'. The first row contains 'NONCOMP', 'NONCOMP', and 'Non Compliance to standards agreed'. Below the table is a text input field containing the text: 'This work does not meet the compliance standards agreed for this subcontract'.

Maintain Creditor Type

You are able to setup different creditor types in order to assist with analysis and reporting of your creditors. There are a number of reports available to assist this.

See Module Guide for Creditors

Workflow

Event Maintenance

Event Maintenance is used for implementation specific workflow processes. For example, this function can be set up for establishing Go/Get percentages for Unsecured Works, or ETS

System Administration

follow-up notifications and is specific to each module. Please contact your consultant for further details.

> **System Administration > Configure Modules > Workflow > Event Maintenance.**

Maintain Email Addresses

You can maintain the email addresses for Debtors, Creditors, Employees, Users, Jobs and RCTI Subcontract Payment Authorities in one central location.

> **System Administration > Configure Modules > Workflow > Maintain Email Addresses.**

Type	Type Desc	Code	Code Description	Seq #	Email Address
U	User Id	ALNPETO	Peter Alnas - Jobpac	1	peter.alnas@viewpoint.com
U	User Id	BADLESO	Lesley Badelles - Viewpoint	10	lesley.badelles@viewpoint.com
U	User Id	BEAGLEO	Glenys BeaumontJC Jobpac	10	glenys.beaumont@viewpoint.com
U	User Id	BOUDAMO	Damien Bourke 0	10	damien.bourke@viewpoint.com
U	User Id	BOUDAM1	Damien Bourke 1	10	damien.bourke@viewpoint.com
U	User Id	DAVGRAO	Grant Davis - Jobpac	10	grant.davis@viewpoint.com
U	User Id	HETOMO	Tom He - Jobpac 2	10	tom.he@viewpoint.com
U	User Id	INGCHAO	Chamika Ingilizian	10	chamika.ingilizian@viewpoint.com
U	User Id	JURWILO	Wilma Juridico - Jobpac	10	wilma.juridico@viewpoint.com
U	User Id	KASSAMO	Saman Kashanchi- Jobpac	10	saman.kashanchi@viewpoint.com

The default display is for Users, which is the basis of signing on to Jobpac.

The Employee code is used in the ETS System.

The creditor code is used for Remittance Advices and Purchase Orders.

The **Add New Contact** function in the Actions menu is used to add a new code. Select from the valid types as shown in the table selected from the Prompt.

Type	Description
C	Creditor
D	Debtor
E	Employee
J	Job
U	User Id

JOM Forms Module

Forms Maintenance

This is available under

> **System Administration > Configure Modules > Forms Module > Definition Maintenance.**

This function is used to support existing users of the JOM (Jobpac Output Module). If this is set up to select forms by type rather than for all forms then the following table determines which form will be used and which one will be ignored.

JFM - Forms Maintenance Program				
Contains		Contains		=
Form Name	Form Description	Default For All Users	Hide Flag	
FORMAP001	Remittance advice	Y	N	
FORMAP003	AP Payment Schedule	Y	N	
FORMAR001	Tax invoice	Y	N	
FORMAR002	Tax invoice	Y	N	
FORMAR003	Statement	Y	N	
FORMCQ001	Cheque	Y	N	
FORMCQ002	Cheque overflow	Y	N	
FORMPC001	Progress claim	Y	N	
FORMPO001	Purchase order	Y	N	
FORMPY001	Payslip	Y	N	
FORMPY002	EFT Payment Summary	Y	N	
FORMPY004	PAYG Summary	Y	N	
FORMSC009	Subcontract Retention Held in Trust Statement	Y	N	
FORMSO001	Service order	Y	N	
FORMSO002	Work Order Invoice File	Y	N	
FORMSP001	SC payment schedule summary	Y	N	
FORMSP002	SC payment advice / RCTI	Y	N	

Forms By User

This is available under

> **System Administration > Configure Modules > Forms by User**

This function is used to support existing users of the JOM (Jobpac Output Module). If this is set up to select forms by type rather than for all forms then the following table determines form usage by user, in case some users need JOM forms and others are not to use JOM forms.

JFM - Forms Maintenance Program ACTIONS OK BACK

Hide Apply < > ...

Contains

User	User Name
AITJACO	Jackie Aitchison - Viewpoint
ALNPETO	Peter Alnas - Jobpac
BADLES0	Lesley Badelles - Viewpoint
BEAGLE0	Glenys BeaumontJC Jobpac
BOUDAMO	Damien Bourke 0

Select the forms to be used and not used by an individual user.

JFM - Forms Maintenance Program ACTIONS OK BACK

User ALNPETO Peter Alnas - Jobpac < > ...

Form Name	Form Description	Use JFM	Hide Flag
FORMAP001	Remittance advice	Y	N
FORMAR001	Tax invoice	Y	N
FORMAR002	Tax invoice	Y	N
FORMAR003	Statement	Y	N
FORMCQ001	Cheque	Y	N
FORMCQ002	Cheque overflow	Y	N
FORMPC001	Progress claim	Y	N
FORMPO001	Purchase order	Y	N
FORMPY004	PAYG Summary	Y	N
FORMSO001	Service order	Y	N
FORMSP001	SC payment schedule summary	Y	N

Procurement Approvals

Please discuss with your Jobpac consultant, because this is an additional module. It needs to be set up in detail and more configuration is required.

Further details are available in the **Function Guide for Advance Approvals**

BFM Utilities

Setting up the BFM is undertaken by Jobpac consultants and Application Engineers.

There is a BFM System Administration manual with complete details of the relevant programs. These programs are included in this menu to allow for different administration and control environments.