EM Fundamentals

DISC

2017

Electromagnetics
Fundamentals and Applications

Motivation: applications difficult for DC

Large areas to be covered



Resistive layer “shields” target



Rugged terrain

Hard to inject

Outline

- Basic Survey
- Ampere's and Faraday's Laws (2-coil App)
- Circuit model for EM induction
- Frequency and time domain data
- Sphere in homogeneous earth
- Cyl code
- Energy losses in the ground

Basic Experiment

- **Setup:**
  - transmitter and receiver are in a towed bird



Basic Experiment

- **Setup:**
  - transmitter and receiver are in a towed bird

- **Primary:**
  - Transmitter produces a primary magnetic field



Basic Experiment

- **Setup:**
  - transmitter and receiver are in a towed bird
- **Primary:**
  - Transmitter produces a primary magnetic field
- **Induced Currents:**
  - Time varying magnetic fields generate electric fields everywhere and currents in conductors



Basic Experiment

- **Setup:**
  - transmitter and receiver are in a towed bird
- **Primary:**
  - Transmitter produces a primary magnetic field
- **Induced Currents:**
  - Time varying magnetic fields generate electric fields everywhere and currents in conductors
- **Secondary Fields:**
  - The induced currents produce a secondary magnetic field.



Transmitter





Basic Equations: Quasi-static

	Time 	Frequency
Faraday's Law	$\nabla \times \mathbf{e} = -\dfrac{\partial \mathbf{b}}{\partial t}$	$\nabla \times \mathbf{E} = -i\omega\mathbf{B}$
Ampere's Law	$\nabla \times \mathbf{h} = \mathbf{j} + \dfrac{\partial \mathbf{d}}{\partial t}$	$\nabla \times \mathbf{H} = \mathbf{J} + i\omega\mathbf{D}$
No Magnetic Monopoles	$\nabla \cdot \mathbf{b} = 0$	$\nabla \cdot \mathbf{B} = 0$
Constitutive Relationships (non-dispersive)	$\mathbf{j} = \sigma\mathbf{e}$ $\mathbf{b} = \mu\mathbf{h}$ $\mathbf{d} = \varepsilon\mathbf{e}$	$\mathbf{J} = \sigma\mathbf{E}$ $\mathbf{B} = \mu\mathbf{H}$ $\mathbf{D} = \varepsilon\mathbf{E}$

* Solve with sources and boundary conditions

Ampere's Law

$$\nabla \times \mathbf{H} = \mathbf{J}$$

Wire



$$\mathbf{B} = \frac{\mu_0 I_{enc}}{2\pi r}\hat{\phi}$$

Right hand rule

Current loop

$$\mathbf{B} = \frac{\mu_0 m}{4\pi r^3}(2\cos\theta\hat{\mathbf{r}} + \sin\theta\hat{\boldsymbol{\theta}})$$

$$m = IA$$







Faraday's Law

Lenz' Law

$$\nabla \times \mathbf{e} = -\frac{\partial \mathbf{b}}{\partial t}$$

Ohm's Law

$$\mathbf{j} = \sigma \mathbf{e}$$



Faraday's Law



Faraday's Law

$$\nabla \times \mathbf{e} = -\frac{\partial \mathbf{b}}{\partial t}$$

Magnetic Flux

$$\phi_{\mathbf{b}} = \int_A \mathbf{b} \cdot \hat{\mathbf{n}}\, da$$

ϕ_b : constant

Induced EMF

$$V = EMF = -\frac{d\phi_{\mathbf{b}}}{dt} = \mathbf{0}$$





Faraday's Law

$$\nabla \times \mathbf{e} = -\frac{\partial \mathbf{b}}{\partial t}$$

Magnetic Flux

$$\phi_{\mathbf{b}} = \int_A \mathbf{b} \cdot \hat{\mathbf{n}}\, da$$

ϕ_b :



Induced EMF

$$V = EMF = -\frac{d\phi_{\mathbf{b}}}{dt} < 0$$



Faraday's Law

$$\nabla \times \mathbf{e} = -\frac{\partial \mathbf{b}}{\partial t}$$

Magnetic Flux

$$\phi_{\mathbf{b}} = \int_A \mathbf{b} \cdot \hat{\mathbf{n}}\, da$$

Induced EMF

$$V = EMF = -\frac{d\phi_{\mathbf{b}}}{dt} > 0$$





App for Faraday's Law

2 Apps:

- Harmonic
- Transient

Lenz' Law

$$\nabla \times \mathbf{e} = -\frac{\partial \mathbf{b}}{\partial t}$$

$$\mathbf{j} = \sigma \mathbf{e}$$





http://em.geosci.xyz/apps.html

Two Coil Example: Transient

Primary currents

Magnetic flux

Time-variation of magnetic flux

Secondary currents







$$I_s(t) = I_s e^{-t/\tau}$$

$$\tau = L/R$$

Response Function: Transient

Step-off current in Tx



Time constant



$$\tau = L/R$$

Response function: $q(t) = e^{-t/\tau}$





Transient and Harmonic Signals

We have seen a transient pulse…



What happens when he have a harmonic?



Two Coil Example: Harmonic

Induced Currents



$$I_p(t) = I_p \cos \omega t$$

$$I_s(t) = I_s \cos(\omega t - \psi)$$

$$= \underbrace{I_s \cos \psi}_{\text{In-Phase Real}} \cos \omega t + \underbrace{I_s \sin \psi}_{\text{Out-of-Phase Quadrature Imaginary}} \sin \omega t$$

Phase Lag

$$\psi = \frac{\pi}{2} + \tan^{-1}\left(\frac{\omega L}{R}\right)$$





Two Coil Example: Harmonic

Induced Currents



$$I_p(t) = I_p \cos \omega t$$

$$I_s(t) = I_s \cos(\omega t - \psi)$$

$$= \underbrace{I_s \cos \psi}_{\text{In-Phase Real}} \cos \omega t + \underbrace{I_s \sin \psi}_{\text{Out-of-Phase Quadrature Imaginary}} \sin \omega t$$



Phase Lag

$$\psi = \frac{\pi}{2} + \tan^{-1} \underbrace{\left(\frac{\omega L}{R} \right)}_{\alpha}$$

Induction number



Response Function

- Quantifies how a target responds to a time varying magnetic field
- Partitions real and imaginary parts



Response Function



$$\alpha = \frac{\omega L}{R}$$



Response Functions: Summary

Step-off



Harmonic





In both:

- Induce currents

$$\nabla \times \mathbf{e} = -\frac{\partial \mathbf{b}}{\partial t}$$

- Generate secondary magnetic fields

$$\nabla \times \mathbf{h} = \mathbf{j}$$

Secondary magnetic fields

Induced currents generate magnetic fields

- Ampere's Law

$$\nabla \times \mathbf{H} = \mathbf{J}$$



Receiver and Data

Magnetometer

- Measures:
  - Magnetic fields
  - 3 components
- eg. 3-component fluxgate

$$\mathbf{b}(t)$$



Fluxgate

Coil

- Measures:
  - Voltage
  - Single component that depends on coil orientation
    - Coupling matters
- eg. airborne frequency domain
  - ratio of Hs/Hp is the same as Vs/Vp

$$\frac{\partial b}{\partial t}$$



Coil



Coupling

- Transmitter: Primary

$$I_p(t) = I_p \cos(\omega t)$$

$$\mathbf{B}_p(t) \sim I_p cos(\omega t)$$

- Target: Secondary

$$EMF = -\frac{\partial \phi_{\mathbf{B}}}{\partial t}$$
$$= -\frac{\partial}{\partial t}\left(\mathbf{B}_p \cdot \hat{\mathbf{n}}\right) A$$



Circuit model of EM induction





Coupling coefficient

- Depends on geometry

$$M_{12} = \frac{\mu_0}{4\pi} \oint \oint \frac{dl_1 \cdot dl_2}{|\mathbf{r} - \mathbf{r}'|^2}.$$

Magnetic field at the receiver

$$\frac{H^s}{H^p} = -\frac{M_{12}M_{23}}{M_{13}L} \underbrace{\left[\frac{\alpha^2 + \imath\alpha}{1+\alpha^2}\right]}_{Q}$$

Induction Number

- Depends on properties of target

$$\alpha = \frac{\omega L}{R}$$



Conductor in a resistive earth: Frequency

Profile over the loop



- Induction number

$$\alpha = \frac{\omega L}{R}$$

- When $\alpha = 1$
  - Real = Imag





Conductor in a resistive earth: Frequency

Profile over the loop



- Induction number

$$\alpha = \frac{\omega L}{R}$$

- When $\alpha < 1$
  - Real < Imag





Conductor in a resistive earth: Frequency

Profile over the loop



- Induction number

$$\alpha = \frac{\omega L}{R}$$

- When $\alpha > 1$
  - Real > Imag





Conductor in a resistive earth: Transient

Profile over the loop





- Time constant

$$\tau = L/R$$

- Step-off current in Tx



- Response function depends on time, τ

$$q(t) = e^{-t/\tau}$$



Recap: what have we learned?

- Basics of EM induction
- Response functions
- Mutual coupling
- Data for frequency or time domain systems

- Circuit model provides representative results
  - Applicable to geologic targets?



Sphere in a resistive background

How representative is a circuit model?









Cyl Code

- Finite Volume EM
  - Frequency and Time



- Built on SimPEG

- Open source, available at:

http://em.geosci.xyz/apps.html

- Papers

Cockett et al, 2015

Heagy et al, 2017



Recap: what have we learned?

- Basics of EM induction
- Response functions
- Mutual coupling
- Data for frequency or time domain systems
- Circuit model is a good proxy

2-Coil Apps

- Frequency domain
- Time domain

Major item not yet accounted for…

- Propagation of energy from
  - Transmitter to target
  - Target to receiver



How do EM fields and fluxes behave in a conductive background?

Revisit Maxwell's equations

First order equations

$$\nabla \times \mathbf{e} = -\frac{\partial \mathbf{b}}{\partial t} \qquad \mathbf{j} = \sigma \mathbf{e}$$

$$\nabla \times \mathbf{h} = \mathbf{j} + \frac{\partial \mathbf{d}}{\partial t} \qquad \mathbf{b} = \mu \mathbf{h}$$

$$\mathbf{d} = \varepsilon \mathbf{e}$$

Second order equations

$$\nabla^2 \mathbf{h} - \underbrace{\mu\sigma \frac{\partial \mathbf{h}}{\partial t}}_{\text{diffusion}} - \underbrace{\mu\epsilon \frac{\partial^2 \mathbf{h}}{\partial t^2}}_{\substack{\text{wave} \\ \text{propagation}}} = 0$$

In frequency

$$\nabla^2 \mathbf{H} + k^2 \mathbf{H} = 0$$

$$k^2 = \omega^2 \mu\varepsilon - i\omega\mu\sigma$$

* Same equation holds for E

Plane waves in a homogeneous media

In frequency

$$\nabla^2 \mathbf{H} + k^2 \mathbf{H} = 0$$

$$k^2 = \omega^2 \mu\varepsilon - i\omega\mu\sigma$$

Quasi-static

$$\frac{\omega\varepsilon}{\sigma} \ll 1$$

even if…

$$\sigma = 10^{-4} S/m$$

$$f = 10^4 Hz$$

then

$$\frac{\omega\varepsilon}{\sigma} \sim 0.005$$

$$k = \sqrt{-i\omega\mu\sigma} = (1-i)\sqrt{\frac{\omega\mu\sigma}{2}}$$

$$\equiv \alpha - i\beta$$

Plane wave solution



$$\mathbf{H} = \mathbf{H_0} \underbrace{e^{-\alpha z}}_{\text{attenuation}} \underbrace{e^{-i(\beta z - \omega t)}}_{\text{phase}}$$

Skin depth

δ : skin depth



$$\delta = \sqrt{\frac{2}{\omega\mu\sigma}} = 503\sqrt{\frac{1}{\sigma f}}$$

Plane waves in a homogeneous media

In time

$$\nabla^2 \mathbf{h} - \mu\epsilon \frac{\partial^2 \mathbf{h}}{\partial t^2} - \mu\sigma \frac{\partial \mathbf{h}}{\partial t} = 0$$

$$\mathbf{h}(t=0) = \mathbf{h}_0 \delta(t)$$

Solution for quasi-static

$$\mathbf{h}(t) = -\frac{(\mu\sigma)^{1/2} z}{2\pi^{1/2} t^{3/2}} e^{-\mu\sigma z^2/(4t)}$$

z: depth (m)

Peak time:



$$t_{max} = \frac{\mu\sigma z^2}{6}$$

Diffusion distance



$$d = \sqrt{\frac{2t}{\mu\sigma}}$$

$$\approx 1260\sqrt{\frac{t}{\sigma}}$$

Plane Wave apps

- 2 apps:
  - Transient

$$\mathbf{h}(t) = -\frac{(\mu\sigma)^{1/2} z}{2\pi^{1/2} t^{3/2}} e^{-\mu\sigma z^2/(4t)}$$

  - Harmonic

$$\mathbf{H} = \mathbf{H_0} \underbrace{e^{-\alpha z}}_{\text{attenuation}} \underbrace{e^{-i(\beta z - \omega t)}}_{\text{phase}}$$





http://em.geosci.xyz/apps.html

Effects of background resistivity



Effects of background resistivity: Time

- Buried, conductive sphere
- Vary background conductivity

- Time: 10^{-5} s



10^{-8} S/m background



Current Density



Effects of background resistivity: Time

- Buried, conductive sphere
- Vary background conductivity

- Time: 10^{-5} s



10^{-2} S/m background



Current Density



Effects of background resistivity: Time

- Buried, conductive sphere
- Vary background conductivity

- Time: 10^{-5} s



10^{-1} S/m background



Current Density



Effects of background resistivity: Time

- Buried, conductive sphere
- Vary background conductivity

- Time: 10^{-5} s



1 S/m background



Current Density



10^{-5} s

Effects of background resistivity: Time

10^{-8} S/m



10^{-2} S/m



10^{-1} S/m



1 S/m



Effects of background resistivity



Effects of background resistivity: Frequency

- Buried, conductive sphere
- Vary background conductivity

- Frequency: 10^4 Hz



10^{-8} S/m background



Current Density



Effects of background resistivity: Frequency

- Buried, conductive sphere
- Vary background conductivity

- Frequency: 10^4 Hz



10^{-2} S/m background



Current Density



Effects of background resistivity: Frequency

- Buried, conductive sphere
- Vary background conductivity

- Frequency: 10^4 Hz



10^{-1} S/m background



Current Density



Effects of background resistivity: Frequency

- Buried, conductive sphere
- Vary background conductivity

- Frequency: 10^4 Hz



1 S/m background



Current Density



Effects of background resistivity: Frequency

10^{-8} S/m



10^{-2} S/m



10^{-1} S/m



1 S/m



Recap: what have we learned?

- Basics of EM induction
- Response functions
- Mutual coupling
- Data for frequency or time domain systems
- Circuit model is a good proxy
- Need to account for energy losses

- Ready to look at some field examples



Today's Case Histories



Mt. Isa, Australia:
Mineral Exploration



France: Dam Monitoring



Kasted, Denmark:
mapping paleochannels



Saudi Arabia: Improving
a seismic velocity model



Bookpurnong, Australia:
diagnosing river
salinization



Deccan Traps, India:
mapping sediment beneath
basalt



Barents Sea, Norway:
Hydrocarbon de-risking

Today's Case Histories



Oregon, USA: methane hydrate



Iceland: characterizing geothermal systems



Sweden: Landslides, quick clays



Switzerland: Rock Glaciers



USA: Self-driving vehicles



Denmark: Landfill



Mt. Isa, Australia: Mineral Exploration

End of EM Fundamentals