



**Electric Cloud**  
**ElectricAccelerator**  
version 7.0.1

**Release Notes**

July 15, 2013

These Release Notes contain supplemental information about ElectricAccelerator, version 7.0.1.

Topics include:

Product Description .....	2
What's New for Version 7.0.1 .....	2
Release Notes for Previous 7.0 Versions .....	2
Installation/Upgrade Notes .....	2
Known Issues .....	5
Documentation .....	5
Troubleshooting and Getting Help .....	6

## Product Description

ElectricAccelerator® is a software build accelerator that dramatically reduces software build times by distributing the build over a large cluster of inexpensive servers. Using a patented dependency management system, ElectricAccelerator identifies and fixes problems in real time that would break traditional parallel builds. ElectricAccelerator plugs into existing software development environments seamlessly and includes web-based management and reporting tools.

Electric Cloud also offers ElectricAccelerator Developer Edition, which enables individual developers to leverage the multiple cores in a personal workstation. Instead of running a build sequentially on a single core, ElectricAccelerator Developer Edition runs all of the build's workload in parallel on multiple cores on the local developer desktop.

ElectricAccelerator and ElectricAccelerator Developer Edition include the following components:

- Electric Make® (eMake)
- Electric File System (EFS)
- ElectricAccelerator® Agents (Electric Agent or Agent)
- Cluster Manager
- Electrify

**Note:** The Cluster Manager is a component of ElectricAccelerator only.

## What's New for Version 7.0.1

### Features and Functionality

- You can now use `efpredict` to help verify that the expressions you entered for Electrify's whole command-line matching actually select the correct processes. Refer to the *Electric Make Users Guide* for information about using `efpredict`.

### Resolved Issues

- The option `--emake-readdir-conflicts` is now ignored for parse avoidance purposes. (EC-9934)
- When running concurrent local-mode (no agent) builds on a single host, one or more of the builds could fail. This issue was fixed. (EC-9929)
- When running ClearCase, specifying any `--emake-clearcase` option would cause eMake to abort. This issue was fixed. (EC-9893)

## Release Notes for Previous 7.0 Versions

[Release Notes](#) for version 7.0.

All Accelerator documentation is available on the [Electric Cloud Support web site](#).

## Installation/Upgrade Notes

### *Before You Upgrade*

**Before** upgrading the Cluster Manager...

Ensure you back up this directory: `/opt/ecloud/<arch>/cloud` for UNIX or `C:\ECloud\i686_win32` for Windows, to a safe location to preserve the existing files. The upgrade process does not preserve the existing files.

For additional security, perform a database backup following the recommended procedure for your respective database system.

### **Linux Platforms Require Additional Libraries to Run MySQL on the Cluster Manager**

If you are upgrading from an Accelerator version earlier than 6.2, be advised that the toolchain now includes MySQL 5.5.16 (updated from MySQL 5.0). To run MySQL 5.5.16, the **Cluster Manager must have the 32-bit version of the following libraries:**

- `libaio.so.1`
- `libncurses.so.5`

You may need to add those libraries to the Cluster Manager machine.

#### **RHEL example using a package manager:**

```
yum install libaio.i686
yum install ncurses-libs.i686
```

#### **RHEL example without a package manager:**

```
up2date --nox --arch=i386 libaio
up2date --nox --arch=i386 ncurses
```

#### **Ubuntu example using a package manager:**

```
apt-get install libaio1
```

The installer will notify you if the libraries are missing but will complete the installation process with a message similar to the following: The upgrade of MySQL to 5.5 had problems. Please contact customer support for additional help. The install log will also contain a message similar to the following: FATAL ERROR: Can't execute '/opt/ecloud/i686\_Linux/mysql/bin/mysql'

If you attempt to start the Cluster Manager without the required libraries, the UI may display a Server Startup Status page with a Server State of `databaseConnection`.

### **Known Linux Kernel Issue and ElectricAccelerator Performance**

#### **Affected Kernel Versions**

- RHEL versions later than 2.6.18-194.32 and earlier than 2.6.32-131.
- Ubuntu versions 2.6.31, 32, 33, and 34

#### **Symptoms**

Affected systems may encounter reduced performance on both ext3 and ext4 filesystems. Symptoms may include:

- `hung_task_timeout_secs` messages in system `dmesg` logs
- widely variable agent availability (entering and exiting agent "penalty" status frequently)
- contention over the `ecagent.state` file
- slower builds (with unexplained variances)

To help determine if your environment has this kernel issue, run

```
dmesg | grep hung_task_timeout
```

If `hung_task_timeout` errors are present, this indicates that a known Linux kernel issue is present. Contact your kernel provider to obtain a different version of the precompiled kernel.

### Corrective Actions

#### For systems running RHEL 5.6, 5.7, 5.8, and 6.0

Consider upgrading to 2.6.32-131 (RHEL 6.1), or downgrading to 2.6.18-194.32 (RHEL 5.5).

#### For systems running Ubuntu 10.04

Consider upgrading to kernel version 2.6.35 or later.

To install the upstream kernel, do the following, for example (replace \* with the version you want to install):

```
sudo add-apt-repository ppa:kernel-ppa/ppa
sudo aptitude update
sudo apt-get install linux-image-2.6.35-*--generic
sudo apt-get install linux-headers-2.6.35-*--generic
sudo apt-get install linux-maverick-source-2.6.35 linux-maverick-headers-2.6 (optional)
```

Upgrading the kernel may require you to reinstall various kernel modules such as video drivers, `efs`, and `vm-tools`. You can do so by running: `apt-get dist-upgrade` and then rebooting.

### Cluster Manager Installs

If Apache fails to start properly after a fresh Cluster Manager install, reboot the system.

### ECLOCK\_TIMEOUT\_DELAY

If you currently set the `eclock ECLOCK_TIMEOUT_DELAY` environment variable, it is no longer used and can be deleted. To replace the environment variable's behavior, divide the value of `ECLOCK_TIMEOUT_DELAY` by 100, and set `ECLOCK_BUSY_WAIT` to the resulting value. (The `ECLOCK_BUSY_WAIT` default value is 100, so you do not need to set it to that value explicitly.)

### Linux Automounted Filesystems

If you previously implemented a workaround for automounted filesystems on Linux (such as hard mounting filesystems or manually changing the automounter configuration) you can undo those changes after you upgrade to the latest version of ElectricAccelerator.

### Clarification - Windows Application Setup

Any Windows applications that store user-specific data must be run [on all hosts] by the user who owns the agent processes on those hosts.

For example, if you plan to use Microsoft Visual Studio, you must log in to each agent host and run `devenv` as the user that owns the respective agent processes (usually `ECloudInternalUser1`, `ECloudInternalUser2`, and so on). You can use the `psexec` tool (downloadable from <http://technet.microsoft.com/en-us/sysinternals/bsb896649.aspx>) to eliminate the need to log in and log out multiple times. Using this tool is more efficient because some applications such as Visual Studio or Excel store user settings in the registry and create files in "My Documents."

If you install Visual Studio after installing ElectricAccelerator, register the add-in on the hosts by running `install_ecaddin<N>.bat` where `N` is 70, 71, 80, 90, 100, or 110 depending on your Visual Studio version.

If you are using Visual Studio 2005 or later, reduce the number of parallel builds Visual Studio performs:

1. In Visual Studio, select Tools > Options.
2. In the Options dialog, open Projects and Solutions > Build and Run.
3. Set maximum number of parallel project builds to 1.

When setting up Windows, be sure to initialize the Customer Experience Improvement Program setting.

## Known Issues

This version of ElectricAccelerator has the following known issues :

- For Visual Studio 2012, the project build order under eMake may be different to Visual Studio if project dependencies are not fully defined.

Workaround: If a build fails because a prerequisite project has not been built, add an explicit project dependency in the solution.

## Documentation

ElectricAccelerator documentation is available on the Electric Cloud Support web site at <https://electriccloud.zendesk.com/entries/22575906-electricaccelerator-documentation>. Updated documentation will be available on that page if any documents are updated post-release.

ElectricAccelerator provides the following product documentation:

- *ElectricAccelerator Installation and Configuration Guide* also available within the online help system
- *ElectricAccelerator Electric Make Users Guide* also available within the online help system
- *ElectricAccelerator cmtool Reference and Users Guide* also available within the online help system
- A complete, robust online help system - click any Help link in the upper-right corner of each web page.
- Tooltips with information to help fill-in form fields (information also available in online help topics).
- ElectricAccelerator Technical Notes:
  - ElectricAccelerator - Visual Studio IDE Add-in
  - ElectricAccelerator - Solution Support Add-in
- *ElectricAccelerator Release Notes*

## Troubleshooting and Getting Help

Contacting Technical Support:

*Before* you contact our technical support staff, please have the following information available.

- Your name, title, company name, phone number, fax number, and email address
- Operating system and version number
- Product name and release version
- Problem description

**Hours:** 8AM - 5PM PST (Monday-Friday, except Holidays)

**Phone:** 408-419-4300, Option #2

**Email:** support@electric-cloud.com

Copyright © 2002 - 2013 Electric Cloud, Inc. All rights reserved.

Electric Cloud® believes the information in this publication is accurate as of its publication date. The information is subject to change without notice.

THE INFORMATION IN THIS PUBLICATION IS PROVIDED "AS IS." ELECTRIC CLOUD, INC. MAKES NO REPRESENTATIONS OR WARRANTIES OF ANY KIND WITH RESPECT TO THE INFORMATION IN THIS PUBLICATION, AND SPECIFICALLY DISCLAIMS IMPLIED WARRANTIES OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE.

Use, copying, and distribution of any Electric Cloud software described in this publication requires an applicable software license.

### Trademarks

Electric Cloud, ElectricAccelerator, ElectricCommander, ElectricInsight, and Electric Make are registered trademarks or trademarks of Electric Cloud, Incorporated.

Electric Cloud products—ElectricAccelerator, ElectricCommander, ElectricInsight, and Electric Make—are commonly referred to by their "short names"—Accelerator, Commander, Insight, and eMake—throughout various types of Electric Cloud product-specific documentation.

All other trademarks used herein are the property of their respective owners.