



# **Zenoss Core Upgrade Guide**

Release 5.1.4

Zenoss, Inc.

[www.zenoss.com](http://www.zenoss.com)

# Zenoss Core Upgrade Guide

Copyright © 2016 Zenoss, Inc. All rights reserved.

Zenoss and the Zenoss logo are trademarks or registered trademarks of Zenoss, Inc., in the United States and other countries. All other trademarks, logos, and service marks are the property of Zenoss or other third parties. Use of these marks is prohibited without the express written consent of Zenoss, Inc., or the third-party owner.

Flash is a registered trademark of Adobe Systems Incorporated.

Oracle, the Oracle logo, Java, and MySQL are registered trademarks of the Oracle Corporation and/or its affiliates.

Linux is a registered trademark of Linus Torvalds.

RabbitMQ is a trademark of VMware, Inc.

SNMP Informant is a trademark of Garth K. Williams (Informant Systems, Inc.).

Sybase is a registered trademark of Sybase, Inc.

Tomcat is a trademark of the Apache Software Foundation.

VMware is a registered trademark or trademark of VMware, Inc. in the United States and/or other jurisdictions.

Windows is a registered trademark of Microsoft Corporation in the United States and other countries.

All other companies and products mentioned are trademarks and property of their respective owners.

Part Number: 1091.16.183

Zenoss, Inc.  
11305 Four Points Drive  
Bldg 1 - Suite 300  
Austin, Texas 78726

# Contents

<b>About this guide.....</b>	<b>4</b>
<b>Chapter 1: Supported software and upgrade paths.....</b>	<b>6</b>
Release dates and versions.....	6
Supported upgrade paths included in this document.....	7
Upgrade paths included in previous versions.....	7
<b>Part I: Upgrading only Control Center.....</b>	<b>9</b>
<b>Chapter 2: Upgrading Control Center with internet access.....</b>	<b>10</b>
Stopping applications.....	10
Upgrading the master host.....	10
Upgrading resource pool hosts.....	11
<b>Part II: Upgrading only Zenoss Core.....</b>	<b>13</b>
<b>Chapter 3: Upgrading Zenoss Core with internet access.....</b>	<b>14</b>
Stopping applications.....	14
Upgrading Zenoss Core.....	14
<b>Chapter 4: After upgrading.....</b>	<b>16</b>
Deleting the pre-upgrade snapshot.....	16
<b>Appendix A: Using Zenoss Toolbox.....</b>	<b>17</b>
Zenoss Toolbox tools.....	17
Downloading Zenoss Toolbox with internet access.....	17
Installing Zenoss Toolbox.....	18
Running Zenoss Toolbox tools.....	18

# About this guide

*Zenoss Core Upgrade Guide* provides detailed instructions for upgrading Zenoss Core from one minor or micro version to a more recent version.

---

**Note** Zenoss strongly recommends reviewing the *Zenoss Core Planning Guide* carefully before using this guide.

---

## Related publications

Title	Description
<i>Zenoss Core Administration Guide</i>	Provides an overview of Zenoss Core architecture and features, as well as procedures and examples to help use the system.
<i>Zenoss Core Configuration Guide</i>	Provides required and optional configuration procedures for Zenoss Core, to prepare your deployment for monitoring in your environment.
<i>Zenoss Core Installation Guide</i>	Provides detailed information and procedures for creating deployments of Control Center and Zenoss Core.
<i>Zenoss Core Planning Guide</i>	Provides both general and specific information for preparing to deploy Zenoss Core.
<i>Zenoss Core Release Notes</i>	Describes known issues, fixed issues, and late-breaking information not already provided in the published documentation set.
<i>Zenoss Core Upgrade Guide</i>	Provides detailed information and procedures for upgrading deployments of Zenoss Core.

## Additional information and comments

Zenoss welcomes your comments and suggestions regarding our documentation. To share your comments, please send an email to [docs@zenoss.com](mailto:docs@zenoss.com). In the email, include the document title and part number. The part number appears at the end of the list of trademarks, at the front of this guide.

## Change history

The following list associates document part numbers and the important changes to this guide since the previous release. Some of the changes involve features or content, but others do not. For information about new or changed features, refer to the *Zenoss Core Release Notes*.

### 1091.16.183

Add new version numbers.

### 1091.16.153

Add new version numbers.

### 1091.16.146

Add new version numbers.

### 1091.16.126

Refine the procedure for creating the application data thin pool.

### 1091.16.118

Add a new part for upgrading only Zenoss Core.

Modify supported upgrade paths for Zenoss Core 5.1.2.

Add a substep to create the docker override directory.

#### 1091.16.111

Add information about Control Center 1.1.3.

#### 1091.16.102

Include instructions to create a `systemd` override file instead of editing the Docker service definition file.

Correct the `Btrfs` filesystem cleanup command.

Add a symlink to `/tmp` in `/var/lib/docker`.

Update the commands for starting and testing a ZooKeeper ensemble.

Add a procedure for updating the `SERVICED_ZK` value on resource pool hosts that are not members of a ZooKeeper ensemble.

Add a reference topic for the ZooKeeper variables required on hosts in a Control Center cluster.

Improve titles in the post-upgrade chapter.

#### 1091.16.068

Add a list of links to the overview of Part I.

After converting the storage driver, perform a full backup.

The Docker configuration file needs a longer startup timeout value, to work around a known Docker issue with the `devicemapper` driver. All Docker configuration steps now include adding `TimeoutSec=300`.

#### 1091.16.067

A new part is added, for upgrading only Control Center. Both parts are renamed to reflect the addition.

The scope of supported upgrade paths is changed to reflect the micro release of Control Center.

All Docker configuration steps now add the storage driver flag (`-s devicemapper`) to the `/etc/sysconfig/docker` file.

All resource pool host upgrade procedures include a step to unmount the distributed file system before restarting `serviced`.

A link to the post-upgrade chapter is added to the end of upgrade procedures, if one is available.

#### 1091.16.060.1

Upgrades are grouped in parts by scope. Each part contains a preparation chapter, chapters for the supported upgrade paths, and a post-upgrade chapter. Only the latest scope is in this version of the guide; previous scopes are in earlier versions.

A description of Zenoss Toolbox is included as an appendix.

## 1

## Supported software and upgrade paths

---

Beginning with version 5.0.0, distributions of Zenoss Core include an additional component, Control Center. Each component is developed and maintained separately, and each has its own version number. This chapter identifies the combinations of component versions that Zenoss supports, and the supported upgrade paths between the combinations.

### Release dates and versions

Release Date	Control Center	Zenoss Core
30 Jun 2016	1.1.6	5.1.4
1 Jun 2016	1.1.5	5.1.3
24 May 2016	1.1.4 (withdrawn)	5.1.3
27 Apr 2016	1.1.3	5.1.2
20 Apr 2016	1.1.3	5.1.1
4 Mar 2016	1.1.2	5.1.1
29 Feb 2016	1.1.1	5.1.1
20 Feb 2016	1.0.10	5.0.10
02 Dec 2015	1.0.9	5.0.9
16 Nov 2015	1.0.8	5.0.8
10 Oct 2015	1.0.7	5.0.7
14 Sep 2015	1.0.6	5.0.6
05 Aug 2015	1.0.5	5.0.5
10 Jul 2015	1.0.4	5.0.4
27 May 2015	1.0.3	5.0.3
20 Apr 2015	1.0.2	5.0.2
03 Apr 2015	1.0.1	5.0.1
24 Feb 2015	1.0.0	5.0.0

## Supported upgrade paths included in this document

---

### Upgrade only Control Center

From	To
Control Center 1.1.1	Control Center 1.1.6
Control Center 1.1.2	Control Center 1.1.6
Control Center 1.1.3	Control Center 1.1.6
Control Center 1.1.5	Control Center 1.1.6

### Upgrade only Zenoss Core

From	To
Zenoss Core 5.1.1	Zenoss Core 5.1.4
Zenoss Core 5.1.2	Zenoss Core 5.1.4
Zenoss Core 5.1.3	Zenoss Core 5.1.4

## Upgrade paths included in previous versions

---

The following tables identify upgrade paths that are supported but documented only in previous editions of this guide.

**Table 1: Upgrade from 1.0.x / 5.0.x to 1.1.x / 5.1.x**

From combination	To combination
Control Center 1.0.6 and Zenoss Core 5.0.6	Control Center 1.1.5 and Zenoss Core 5.1.3
Control Center 1.0.7 and Zenoss Core 5.0.7	Control Center 1.1.5 and Zenoss Core 5.1.3
Control Center 1.0.8 and Zenoss Core 5.0.8	Control Center 1.1.5 and Zenoss Core 5.1.3
Control Center 1.0.9 and Zenoss Core 5.0.9	Control Center 1.1.5 and Zenoss Core 5.1.3
Control Center 1.0.10 and Zenoss Core 5.0.10	Control Center 1.1.5 and Zenoss Core 5.1.3

**Table 2: Upgrade to 1.0.10 / 5.0.10**

From combination	To combination
Control Center 1.0.3 and	Control Center 1.0.10 and

From combination	To combination
Zenoss Core 5.0.3	Zenoss Core 5.0.10
Control Center 1.0.4 and Zenoss Core 5.0.4	Control Center 1.0.10 and Zenoss Core 5.0.10
Control Center 1.0.5 and Zenoss Core 5.0.5	Control Center 1.0.10 and Zenoss Core 5.0.10
Control Center 1.0.6 and Zenoss Core 5.0.6	Control Center 1.0.10 and Zenoss Core 5.0.10
Control Center 1.0.7 and Zenoss Core 5.0.7	Control Center 1.0.10 and Zenoss Core 5.0.10
Control Center 1.0.8 and Zenoss Core 5.0.8	Control Center 1.0.10 and Zenoss Core 5.0.10
Control Center 1.0.9 and Zenoss Core 5.0.9	Control Center 1.0.10 and Zenoss Core 5.0.10

**Table 3: Upgrade to 1.0.3 / 5.0.3**

From combination	To combination
Control Center 1.0.0 and Zenoss Core 5.0.0	Control Center 1.0.3 and Zenoss Core 5.0.3
Control Center 1.0.1 and Zenoss Core 5.0.1	Control Center 1.0.3 and Zenoss Core 5.0.3
Control Center 1.0.2 and Zenoss Core 5.0.2	Control Center 1.0.3 and Zenoss Core 5.0.3



# Part I: Upgrading only Control Center

The chapters in this part provide instructions for upgrading Control Center without upgrading Zenoss Core.

---

**Note** Before upgrading only Control Center, make sure that you are upgrading to a supported combination of Control Center and Zenoss Core.

---

The following table identifies the supported upgrades of Control Center alone.

From	To
Control Center 1.1.1	Control Center 1.1.6
Control Center 1.1.2	Control Center 1.1.6
Control Center 1.1.3	Control Center 1.1.6
Control Center 1.1.5	Control Center 1.1.6

To perform an upgrade, proceed to [Upgrading Control Center with internet access](#) on page 10.

# Upgrading Control Center with internet access

# 2

This chapter includes detailed procedures for upgrading Control Center cluster hosts that have internet access.

## Stopping applications

This procedure stops all Control Center applications.

- 1 Log in to the Control Center master host as `root`, or as a user with superuser privileges.
- 2 Stop Zenoss Core, and then verify it is stopped.
  - a Stop Zenoss Core.

```
serviced service stop Zenoss.core
```

- b Verify the application is stopped.

Repeat the following command until the `STATUS` column reads `Stopped`:

```
serviced service status Zenoss.core
```

## Upgrading the master host

This procedure upgrades the Control Center master host to version 1.1.6.

- 1 Log in to the master host as `root`, or as a user with superuser privileges.
- 2 Verify that accidental upgrades of Docker are disabled.
  - a Check the Docker repository.

```
grep enabled /etc/yum.repos.d/docker.repo
```

If the result is `enabled=1`, perform the following substeps.

- b Open `/etc/yum.repos.d/docker.repo` with a text editor.
  - c Change the value of the `enabled` key from 1 to 0.
  - d Save the file and close the text editor.
- 3 Stop Control Center.

```
systemctl stop serviced
```

- 4 Install the new version of Control Center.

```
yum --enablerepo=zenoss-stable install -y serviced-1.1.6
```

The installation preserves the existing version of the `serviced` configuration file, and installs the new one as `/etc/default/serviced.rpmnew`.

- 5 Delete the new Control Center configuration file.

There are no configuration file changes in this release.

```
rm /etc/default/serviced.rpmnew
```

- 6 Start Control Center.

```
systemctl start serviced
```

- **Single-host deployments:** You may log in to the Control Center browser interface, and then restart Zenoss Core, if desired.
- **Multi-host deployments:** Update all resource pool hosts (the next procedure).

## Upgrading resource pool hosts

---

This procedure upgrades Control Center resource pool hosts to version 1.1.6.

Perform this procedure on each resource pool host in your deployment.

- 1 Log in to the resource pool host as `root`, or as a user with superuser privileges.
- 2 Verify that accidental upgrades of Docker are disabled.
  - a Check the Docker repository.

```
grep enabled /etc/yum.repos.d/docker.repo
```

If the result is `enabled=1`, perform the following substeps.

- b Open `/etc/yum.repos.d/docker.repo` with a text editor.
  - c Change the value of the `enabled` key from `1` to `0`.
  - d Save the file and close the text editor.
- 3 Stop Control Center and Docker.

```
systemctl stop serviced && systemctl stop docker
```

- 4 Unmount the distributed file system (DFS).
  - a Identify the file system specification to unmount.

```
mount | awk '/serviced/ { print $1 }'
```

- b Unmount the DFS.  
Replace `DFS-Mount` with the file system specification returned in the previous substep:

```
umount DFS-Mount
```

- 5 Install the new version of Control Center.

```
yum --enablerepo=zenoss-stable install -y serviced-1.1.6
```

The installation preserves the existing version of the `serviced` configuration file, and installs the new one as `/etc/default/serviced.rpmnew`.

- 6 Delete the new Control Center configuration file.  
There are no configuration file changes in this release.

```
rm /etc/default/serviced.rpmnew
```

- 7 Start Control Center.

```
systemctl start serviced
```

## Part II: Upgrading only Zenoss Core

The chapters in this part provide instructions for upgrading Zenoss Core without upgrading Control Center.

---

**Note** Before upgrading only Zenoss Core, make sure that you are upgrading to a supported combination of Control Center and Zenoss Core.

---

The following table identifies the supported upgrades of Zenoss Core alone.

From	To
Zenoss Core 5.1.1	Zenoss Core 5.1.4
Zenoss Core 5.1.2	Zenoss Core 5.1.4
Zenoss Core 5.1.3	Zenoss Core 5.1.4

To perform an upgrade, proceed to [Upgrading Zenoss Core with internet access](#) on page 14.

# Upgrading Zenoss Core with internet access

# 3

This chapter includes detailed procedures for upgrading Zenoss Core on hosts that have internet access.

**Note** Zenoss strongly recommends checking the integrity of Zenoss Core databases before performing an upgrade or installing a ZenPack. For more information, see [Using Zenoss Toolbox](#) on page 17.

## Stopping applications

This procedure stops all Control Center applications.

- 1 Log in to the Control Center master host as `root`, or as a user with superuser privileges.
- 2 Stop Zenoss Core, and then verify it is stopped.
  - a Stop Zenoss Core.

```
serviced service stop Zenoss.core
```

- b Verify the application is stopped.

Repeat the following command until the STATUS column reads Stopped:

```
serviced service status Zenoss.core
```

## Upgrading Zenoss Core

This procedure upgrades Zenoss Core.

Before performing this procedure, stop Zenoss Core.

- 1 Log in to the Control Center master host as `root`, or as a user with superuser privileges.
- 2 Download the primary Docker image of Zenoss Core for this release

The download takes approximately 10-20 minutes.

```
docker run -it --rm -v /root:/mnt/root \  
  zenoss/core_5.1:5.1.4_1 rsync -a /root/5.1.x /mnt/root
```

When the download completes, the `rsync` command copies scripts that perform the upgrade to `/root/5.1.x`.

- 3 Pull additional images for Zenoss Core from Docker Hub.

```
/root/5.1.x/pull-docker-images.sh
```

- 4 Start the upgrade script.

```
/root/5.1.x/upgrade-core-5.1.x.sh
```

The upgrade takes about 25-50 minutes.

- 5 Restart Zenoss Core.

Some Zenoss Core services are started during the upgrade, and they need to be restarted.

```
serviced service restart Zenoss.core
```

Proceed to [After upgrading](#) on page 16.

## After upgrading

---

This chapter includes information about what to do after upgrading Zenoss Core.

### Deleting the pre-upgrade snapshot

---

Before the Zenoss Core upgrade begins, the upgrade script creates and tags a snapshot of the system. Tagged snapshots persist until they are explicitly removed. When you are satisfied the new release is working properly, delete the pre-upgrade snapshot.

- 1 Log in to the Control Center master host as `root`, or as a user with superuser privileges.
- 2 Display a list of all Control Center snapshots, with their tags.

```
serviced snapshot list -t
```

Example result:

Snapshot	Description	Tags
xm5mtezbyo2_20160211-220535.480		preupgrade-resmgr-5.1.2

- 3 Delete the pre-upgrade snapshot.

Replace *Snapshot-ID* with the identifier of the pre-upgrade snapshot returned in the previous step:

```
serviced snapshot remove Snapshot-ID
```



## A

# Using Zenoss Toolbox

---

This appendix describes how to install and use Zenoss Toolbox.

## Zenoss Toolbox tools

---

The Zenoss Toolbox tools examine key Zenoss Core components for common issues affecting data integrity. Zenoss recommends running the following tools, in order, before upgrading Zenoss Core:

- 1 The `zodbscan` tool quickly scans the Zope Object Database (ZODB) to provide a preliminary indication of the health of the database, and to determine whether the database needs to be compressed with `zenossdbpack` before upgrading.
- 2 The `findposkeyerror` tool checks objects and their relationships, and provides options for fixing errors.
- 3 The `zenrelationscan` tool checks only ZenRelations between objects.
- 4 The `zencatalogscan` tool checks ZODB object catalogs, which speed up web interface access.

The tools are run inside a Zope container, and the log files for each command are found in `$ZENHOME/log/toolbox`.

## Downloading Zenoss Toolbox with internet access

---

This procedure describes how to download Zenoss Toolbox to a Control Center master host that has internet access.

- 1 Log in to the Control Center master host as `root`, or as a user with superuser privileges.
- 2 Create a temporary directory, and change the current working directory to the temporary directory. The directory must be local (not mounted).

```
mkdir /tmp/toolbox && cd /tmp/toolbox
```

- 3 Download Zenoss Toolbox.

```
myUrl=https://github.com/zenoss/zenoss.toolbox/archive/master.zip
curl -sL --insecure -o master.zip $myUrl
```

- 4 Change the directory and file permissions.

The directory and file must be readable, writable, and executable by all users.

```
chmod -R 777 /tmp/toolbox
```

## Installing Zenoss Toolbox

---

This procedure describes how to install Zenoss Toolbox for use in Control Center Zope containers.

- 1 Log in to the Control Center master host as `root`, or as a user with superuser privileges.
- 2 Start a shell as the `zenoss` user in a Zope container.
  - a Change directory to the temporary location of the Zenoss Toolbox `master.zip` file.

```
cd /tmp/toolbox
```

- b Start an interactive shell in a Zope container and save a snapshot named `InstallZenossToolbox`.

```
mySnap=InstallZenossToolbox
serviced service shell -i -s $mySnap zope bash
```

- c Switch user to `zenoss`.

```
su - zenoss
```

- 3 Install Zenoss Toolbox, and then exit the container.

- a Install Zenoss Toolbox.

```
easy_install /mnt/pwd/master.zip
```

- b Exit the `zenoss` user account.

```
exit
```

- c Exit the Zope container.

```
exit
```

- 4 Commit the named snapshot.

```
serviced snapshot commit $mySnap
```

- 5 Restart the Zope service.

```
serviced service restart zope
```

## Running Zenoss Toolbox tools

---

- 1 Log in to the Control Center master host as a user with `serviced` CLI privileges.
- 2 Start an interactive session in a Zope container.

```
serviced service attach zope/0
```

- 3 Switch user to `zenoss`.

```
su - zenoss
```

- 4 Run the Zenoss Toolbox tools, in order.

For more information about the tools, see [Zenoss Toolbox tools](#) on page 17.

- 5 Exit the zenoss user account.

```
exit
```

- 6 Exit the Zope container.

```
exit
```