

Zenoss Core Upgrade Guide

Release 6.1.2

Zenoss, Inc.

www.zenoss.com

Zenoss Core Upgrade Guide

Copyright © 2018 Zenoss, Inc. All rights reserved.

Zenoss, Own IT, and the Zenoss logo are trademarks or registered trademarks of Zenoss, Inc., in the United States and other countries. All other trademarks, logos, and service marks are the property of Zenoss or other third parties. Use of these marks is prohibited without the express written consent of Zenoss, Inc., or the third-party owner.

Amazon Web Services, AWS, and EC2 are trademarks of Amazon.com, Inc. or its affiliates in the United States and/or other countries.

Flash is a registered trademark of Adobe Systems Incorporated.

Oracle, the Oracle logo, Java, and MySQL are registered trademarks of the Oracle Corporation and/or its affiliates.

Linux is a registered trademark of Linus Torvalds.

RabbitMQ is a trademark of Pivotal Software, Inc.

SNMP Informant is a trademark of Garth K. Williams (Informant Systems, Inc.).

Sybase is a registered trademark of Sybase, Inc.

Tomcat is a trademark of the Apache Software Foundation.

VMware is a registered trademark or trademark of VMware, Inc. in the United States and/or other jurisdictions.

Windows is a registered trademark of Microsoft Corporation in the United States and other countries.

All other companies and products mentioned are trademarks and property of their respective owners.

Part Number: 1691.18.082.22

Zenoss, Inc. 11305 Four Points Drive Bldg 1 - Suite 300 Austin, Texas 78726

Contents

About this guide	4
Tested operating environments	
•	5
Change history	5
Chapter 1: Documented upgrade paths	and upgrade considerations7
Upgrade paths included in this document	3
Chapter 2: Before upgrading	10
Importing Zenoss core image mes	
Chapter 3: Upgrading Zenoss Core	
Upgrading Zenoss Core	
Chapter 4: After upgrading	1/
0 1 10 1	
Clearing neartocat events	
Appendix A: Using Zenoss Toolbox	
Annondiy D. Common ungrade error re	noovony procedures 17
Appendix B: Common upgrade error re	
A snapshot with the given tag already exists	

About this guide

Zenoss Core Upgrade Guide provides detailed instructions for upgrading Zenoss Core to the most recent version.

Note Zenoss strongly recommends reviewing the *Zenoss Core Release Notes* carefully before using this guide.

Tested operating environments

Zenoss Core, Control Center, and operating systems

The following table identifies the tested combinations of Zenoss Core, Control Center, and operating system releases.

Zenoss Core release	Control Center	
	Minimum release	Host OS
6.0.1, 6.1.0, 6.1.1, 6.1.2**	1.5.0	RHEL/CentOS 7.2, 7.3, or 7.4 (64-bit)
5.3.0, 5.3.1, 5.3.2, 5.3.3	1.3.0, 1.3.1, 1.3.2, 1.3.3, 1.3.4, 1.4.0, 1.4.1	RHEL/CentOS 7.1, 7.2, or 7.3 (64-bit)
5.2.0, 5.2.1, 5.2.2, 5.2.3, 5.2.4, 5.2.6*	1.2.0, 1.2.1, 1.2.2, 1.2.3, 1.3.0, 1.3.1, 1.3.2, 1.3.3, 1.3.4, 1.4.0, 1.4.1	RHEL/CentOS 7.1, 7.2, or 7.3 (64-bit)
5.1.9, 5.1.10	1.1.9, 1.2.0	RHEL/CentOS 7.1 or 7.2 (64-bit)
5.1.8	1.1.5, 1.1.6, 1.1.7. 1.1.8, 1.1.9	RHEL/CentOS 7.1 or 7.2 (64-bit)
5.1.7	1.1.5, 1.1.6, 1.1.7, 1.1.8	RHEL/CentOS 7.1 or 7.2 (64-bit)
5.1.6 (internal release only)	(none)	(none)
5.1.4, 5.1.5	1.1.5, 1.1.6, 1.1.7	RHEL/CentOS 7.1 or 7.2 (64-bit)
5.1.3	1.1.2, 1.1.3, 1.1.5	RHEL/CentOS 7.1 or 7.2 (64-bit)
5.1.2	1.1.2, 1.1.3	RHEL/CentOS 7.1 or 7.2 (64-bit)
5.1.1	1.1.1, 1.1.2	RHEL/CentOS 7.1 or 7.2 (64-bit)

Supported clients and browsers

The following table identifies the supported combinations of client operating systems and web browsers.

Client OS	Supported browsers
Windows 7, 10	Internet Explorer 11*
	Firefox 56 and later
	Chrome 61 and later

^{**} Version 6.0.0 - controlled availability

^{*} Version 5.2.5 - withdrawn

^{*} Enterprise mode only; compatibility mode is not tested.

Client OS	Supported browsers
macOS 10.12.3, 10.13	Firefox 56 and later
	Chrome 61 and later
Ubuntu 14.04 LTS	Firefox 56 and later
	Chrome 61 and later

Zenoss Core publications

Title	Description
Zenoss Core Administration Guide	Provides an overview of Zenoss Core architecture and features, as well as procedures and examples to help use the system.
Zenoss Core Configuration Guide	Provides required and optional configuration procedures for Zenoss Core, to prepare your deployment for monitoring in your environment.
Zenoss Core Installation Guide	Provides detailed information and procedures for creating deployments of Control Center and Zenoss Core.
Zenoss Core Planning Guide	Provides both general and specific information for preparing to deploy Zenoss Core.
Zenoss Core Release Notes	Describes known issues, fixed issues, and late- breaking information not already provided in the published documentation set.
Zenoss Core Upgrade Guide	Provides detailed information and procedures for upgrading deployments of Zenoss Core.

Additional information and comments

Zenoss welcomes your comments and suggestions regarding our documentation. To share your comments, please send an email to docs@zenoss.com. In the email, include the document title (*Zenoss Core Upgrade Guide*) and part number (1691.18.082.22).

Change history

The following list associates document part numbers and the important changes to this guide since the previous release. Some of the changes involve features or content, but others do not. For information about new or changed features, refer to the *Zenoss Core Release Notes*.

1691.18.082.22 (6.1.2)

Update release numbers.

1691.18.040.22 (6.1.1)

Update release numbers.

1691.18.009 (6.1.0)

Update release numbers.

1691.17.311.1 (6.0.0)

Document changes for new release.

Update release numbers.

1091.17.268 (5.3.2)

Update release numbers.

1091.17.242 (5.3.1)

Update release numbers.

1091.17.230 (5.3.0)

You can upgrade by using the appliance artifacts or a converged set of non-appliance artifacts. This document is reorganized and updated with associated information.

Update release numbers.

1091.17.171 (5.2.6)

Update release numbers.

About 5.2.5

Version 5.2.5 was withdrawn.

1091.17.122 (5.2.4)

Update release numbers.

1091.17.100 (5.2.3)

Update release numbers.

1091.17.058 (5.2.2)

Update release numbers.

1091.17.044 (5.2.1)

Remove change history entries prior to release 5.2.0.

Add a part about upgrading custom deployments, move scope chapter before the part.

1091.16.335 (5.2.0)

Remove procedures for upgrading Control Center. That information is now in the *Control Center Upgrade Guide*.

Documented upgrade paths and upgrade considerations

1

This chapter identifies the release dates of Control Center and Zenoss Core, and the upgrade paths included in this guide.

Upgrade consideration

Zenoss Core 6.1.x is compatible with Zenoss Service Impact version 5.2.3 or later. If you use Zenoss Service Impact and upgrade to Zenoss Core 6.1.x, you must also upgrade to Zenoss Service Impact 5.2.3 or later.

Release dates and versions

Table 1: Release 6.1.x

Release Date	Control Center	Zenoss Core
15 Mar 2018	1.5.0	6.1.2
14 Feb 2018	1.5.0	6.1.1
07 Dec 2017	1.5.0	6.1.0

Table 2: Release 6.0.x

Release Date	Control Center	Zenoss Core
13 Nov 2017	1.5.0	6.0.1
08 Nov 2017	1.5.0	6.0.0

Table 3: Release 5.3.x

Release Date	Control Center	Zenoss Core
25 Sep 2017	1.4.1	5.3.2
30 Aug 2017	1.4.0	5.3.1
17 Aug 2017	1.4.0	5.3.0

Table 4: Release 5.2.x

Release Date	Control Center	Zenoss Core
06 Jul 2017	1.3.3	5.2.6
19 Jun 2017	1.3.3	5.2.5 (withdrawn)
03 May 2017	1.3.2	5.2.4
06 Apr 2017	1.3.1	5.2.3
09 Mar 2017	1.3.0	5.2.2
27 Feb 2017	1.2.3	5.2.2
31 Jan 2017	1.2.2	5.2.1
16 Dec 2016	1.2.1	5.2.0
28 Nov 2016	1.2.0	5.2.0

Upgrade paths included in this document

Upgrading from Zenoss Core 6.1.0

From	То
Zenoss Core 6.1.1	Zenoss Core 6.1.2
Zenoss Core 6.1.0	Zenoss Core 6.1.2

Upgrading from Zenoss Core 6.0.x

From	То
Zenoss Core 6.0.1	Zenoss Core 6.1.2
Zenoss Core 6.0.0	Zenoss Core 6.1.2

Upgrading from Zenoss Core 5.3.x

From	То
Zenoss Core 5.3.3	Zenoss Core 6.1.2
Zenoss Core 5.3.2	Zenoss Core 6.1.2
Zenoss Core 5.3.1	Zenoss Core 6.1.2
Zenoss Core 5.3.0	Zenoss Core 6.1.2

Upgrading from Zenoss Core 5.2.x

From	То
Zenoss Core 5.2.6	Zenoss Core 6.1.2
Zenoss Core 5.2.4	Zenoss Core 6.1.2

From	То
Zenoss Core 5.2.3	Zenoss Core 6.1.2
Zenoss Core 5.2.2	Zenoss Core 6.1.2
Zenoss Core 5.2.1	Zenoss Core 6.1.2
Zenoss Core 5.2.0	Zenoss Core 6.1.2

Upgrading from Zenoss Core 5.1.x

From	То
Zenoss Core 5.1.10	Zenoss Core 6.1.2
Zenoss Core 5.1.9	Zenoss Core 6.1.2
Zenoss Core 5.1.8	Zenoss Core 6.1.2
Zenoss Core 5.1.7	Zenoss Core 6.1.2
Zenoss Core 5.1.5	Zenoss Core 6.1.2
Zenoss Core 5.1.4	Zenoss Core 6.1.2
Zenoss Core 5.1.3	Zenoss Core 6.1.2
Zenoss Core 5.1.2	Zenoss Core 6.1.2
Zenoss Core 5.1.1	Zenoss Core 6.1.2

2

Before upgrading

Use the procedures in this chapter to import updated Docker images for Zenoss Core into the local registry of the Control Center master host.

Downloading Zenoss Core image files

To perform this procedure, you need:

- A workstation with internet access
- An account on the *Zenoss Community* site.
- A secure network copy program

Use this procedure to

- download required files to a workstation
- copy the files to a Control Center master host
- 1 In a web browser, navigate to the download site, and then log in. The download site is *Zenoss Community*.
- 2 Download the self-installing Docker image files for Zenoss Core.
 - install-zenoss-hbase-24.0.8.run
 - install-zenoss-opentsdb-24.0.8.run
 - install-zenoss-core_6.1-6.1.2_1.run
- 3 Use a secure copy program to copy the files to the Control Center master host.

Importing Zenoss Core image files

Use this procedure to import the Zenoss Core image from self-installing archive files.

- 1 Log in to the master host as root, or as a user with superuser privileges.
- **2** Copy or move the archive files to /root.
- 3 Add execute permission to the files.

chmod +x /root/*.run

4 Change directory to /root.

```
cd /root
```

5 Import the images.

```
for image in install-zenoss-*.run
do
  /bin/echo -en "\nLoading $image..."
  yes | ./$image
done
```

6 List the images in the registry.

```
docker images
```

The result should include one image for each archive file.

7 Optional: Delete the archive files, if desired.

```
rm -i ./install-*.run
```

8 Copy the upgrade scripts from the new Zenoss Core image to /root/6.1.x.

```
docker run -it --rm -v /root:/mnt/root \
  zenoss/core_6.1:6.1.2_1 rsync -a /root/6.1.x /mnt/root
```



3

Upgrading Zenoss Core

This chapter contains the procedures for upgrading a customized deployment of Zenoss Core. Before starting the procedures in this chapter, complete the procedures in *Before upgrading* on page 10.

Note Before performing an upgrade or installing a ZenPack, Zenoss strongly recommends that you check the integrity of Zenoss Core databases. For more information, see *Using Zenoss Toolbox* on page 15.

Stopping Zenoss Core

Use this procedure to stop Zenoss Core.

- 1 Log in to the Control Center master host as a user with serviced CLI privileges.
- 2 Check the status of Zenoss Core.

```
serviced service status --show-fields 'Name, ServiceID, Status'
```

- If the status of all services is stopped, this procedure is complete. Continue to the next procedure.
- If the status is running, perform the remaining steps.
- 3 Stop Zenoss Core.

```
serviced service stop Zenoss.core
```

4 Check the status of Zenoss Core.

```
serviced service status --show-fields 'Name, ServiceID, Status'
```

Repeat the command until the status of all services is stopped.

Upgrading Zenoss Core

Use this procedure to upgrade Zenoss Core.

- 1 Log in to the Control Center master host as root, or as a user with superuser privileges.
- 2 Start the upgrade script.

```
/root/6.1.x/upgrade-core.sh
```

The upgrade process begins. If you encounter errors, see *Common upgrade error recovery procedures* on page 17.

3 Restart Zenoss Core.

Some Zenoss Core services are started during the upgrade, and they must be restarted.

serviced service restart Zenoss.core



4

After upgrading

After Zenoss Core is upgraded, perform the procedures in this chapter.

Removing the pre-upgrade snapshot

The Zenoss Core upgrade script uses Control Center to create and tag a snapshot of the system before it begins the upgrade process. Tagged snapshots persist until they are explicitly removed, and grow over time. When you are satisfied the new release is working properly, remove the pre-upgrade snapshot.

- 1 Log in to the Control Center master host as a user with serviced CLI privileges.
- 2 Display a list of all Control Center snapshots, with their tags.

```
serviced snapshot list -t

Example result, truncated to save space:
```

```
Snapshot Description Tags preupgrade-core-5.2.0
```

The snapshot identifier is shown in the first column.

3 Remove the pre-upgrade snapshot.

Replace Snapshot-ID with the identifier of the pre-upgrade snapshot returned in the previous step:

```
serviced snapshot remove Snapshot-ID
```

Clearing heartbeat events

If you are using the **Daemon Process Down** portlet, zencatalogservice may be listed as down immediately after upgrading to this release. The status is incorrect and can be corrected by using this procedure to clear heartbeat events.

- 1 Log in to the Zenoss Core browser interface as a user with ZenManager or Manager privileges.
- 2 Navigate to **ADVANCED** > **Settings**.
- 3 In the left panel, select **Events**.
- 4 At the bottom of the **Event Configuration** page, click the **Clear** button.

Using Zenoss Toolbox



This appendix provides an introduction to the Zenoss Toolbox, which is included in Zenoss Core. For up-to-date information, refer to the Zenoss Toolbox *KnowledgeBase article*.

Zenoss Toolbox tools

The Zenoss Toolbox tools examine key Zenoss Core components for common issues affecting data integrity. Zenoss recommends running the following tools, in order, before upgrading Zenoss Core:

- 1 The *zodbscan* tool quickly scans the Zope Object Database (ZODB) to provide a preliminary indication of the health of the database, and to determine whether the database needs to be compressed with zenossdbpack before upgrading. The zodbscan tool might instruct you to run the following tools:
 - a The *findposkeyerror* tool checks objects and their relationships, and provides options for fixing errors.
 - **b** The *zenrelationscan* tool checks only ZenRelations between objects.
- 2 The zencatalogscan tool checks ZODB object catalogs, which speed up browser interface access.

The tools are run inside a Zope container, and the log files for each command are found in \$ZENHOME/log/toolbox.

Running Zenoss Toolbox tools

- 1 Log in to the Control Center master host as a user with serviced CLI privileges.
- 2 Start an interactive session in a Zope container.

```
serviced service attach zope/0
```

3 Switch user to zenoss.

```
su - zenoss
```

- 4 Run the Zenoss Toolbox tools, in order.
- 5 Exit the zenoss user account.

exit

zenoss

6 Exit the Zope container.

exit

Common upgrade error recovery procedures



This appendix describes common error messages during upgrades, and provides procedures for recovering and continuing.

A snapshot with the given tag already exists

When an upgrade attempt fails, the upgrade script does not remove the snapshot it creates at the beginning of the upgrade process. Use this procedure to remove the tag of the pre-upgrade snapshot and restart the upgrade. Untagged snapshots are removed when their time-to-live (TTL) expires. The TTL value is defined by the SERVICED_SNAPSHOT_TTL variable in the Control Center configuration file.

- 1 Log in to the Control Center master host as a user with serviced CLI privileges.
- 2 Create a variable for the identifier of the tenant application.

```
myTenant=$(serviced service list Zenoss.core --format='{{.ID}}')
```

3 Display a list of all Control Center snapshots, with their tags.

```
serviced snapshot list -t
```

Example result, truncated to save space:

```
Snapshot Description Tags preupgrade-core-5.2.0
```

The snapshot identifier is shown in the first column.

4 Remove the tag of the pre-upgrade snapshot. Replace *Tag-Name* with the name of the pre-upgrade snapshot that was displayed in the previous step:

5 Restart the upgrade script.

```
/root/6.1.x/upgrade-core.sh
```

serviced snapshot untag \${myTenant} Tag-Name