

Marketplace API for Infinigate CORE

Table of Contents

Marketplace API for Infinigate CORE	1
Getting Setup	2

The Marketplace API introduces an easy-to-use REST API that can be utilized by Partners to integrate their own IT systems without requiring extensive knowledge of the Infinigate CORE platform.


It's primary purpose and aim is to provide a system-agnostic and easy to use REST API for Partners to integrate into their own CRM, ERP and Billing systems quickly and easily, focusing on key business scenarios rather than technical ones.

The essential scenarios that this Marketplace API now enables are:


- Retrieving the Product Catalogue
- Creating and Updating Customer accounts
- Placing Sales (New Purchase), Change (Increase/Decrease), Renewal, and Cancellation orders
- Retrieving Orders and their details
- Listing Subscriptions and their details
- Listing and scheduling Rated Data Reports

Getting Setup

1. Login to CORE via <https://partner.infinigate.cloud> (or your brand if you have one)
2. Navigate to the 'Infinigate Integrations' tab on the left-hand pane
3. You will have a section for "API Integrations" and "MarketplaceAPI" should be listed.
4. Click on MarketplaceAPI and click on "Install"



5. This will take approximately 5 minutes (typically less) to enrol and enable the service.
6. NOTE: If this does not proceed past the "Installing...." Then please contact support@infinigate.cloud or partners@infinigate.cloud for assistance.



7. Once enabled and setup the MarketplaceAPI tile should have a green tick; showing as installed. You will also have a new tab on the left-hand pane called "Marketplace API" (you may need to re-login for this to show).
8. Navigate to the Marketplace API tab and you will have the required four pieces to use the API Integration.

API URL: This is your initial target for API's e.g. <https://api.infinigate.cloud/marketplace/token>, <https://api.infinigate.cloud/marketplace/customers> etc .

Username: This is the username of the API user created by enabling the service; you will need to use this when generating a token. **Subscription Key:** This is your authentication to the API gateway that will be required as a header on all API requests made to <https://api.infinigate.cloud/marketplace>.

Go to Documentation: This will link you to the CloudBlue documentation on how to use & operate the API. The password to the user created will have been sent via email to you; however, you can also reset/change this by going to the "Users" tab, activate the user and then reset password.



Infinigate Cloud

Delme Place
Cams Hall Estate
Delme 3
Fareham
PO16 8UX

www.infinigate.cloud