


PHARSIGHTED


SLOW 10.0 Release Notes

New Features

- Improved Playback Controls
 - Larger scrubber bar
 - Playback frame rate / step control
 - Repeat mode: loop or ping-pong
 - Edit mark-in/out frames by text field




- Improved histogram tool
 - Support for color cameras



PHARSIGHTED

- I/O Manipulation Units
 - Right-click to select units for each I/O manipulation, or type in desired unit when editing value (“clks”, “ns”, “us”, “ms”)



- Various other UI improvements

Bug Fixes

- Improved automatic discovery of cameras on PCs with multiple network adapters
- Mouseover pixel values are no longer affected by image tools (focus / exposure assists)

Known Issues

- Installer is currently for Windows 10 or 11 only
- SLOW files saved with this version will not open in versions of SLOW older than 3.0
- Do not open multiple instances of SLOW software on the same computer
- The histogram displayed may be inaccurate when image adjustments are applied
- If text and/or icons do not display correctly, Windows “Untrusted Font Blocking” may be enabled. To fix, install the fonts in the “C:\Program Files\SLOW\fonts” directory by right-clicking each .ttf font file and clicking “Install for all users”. Alternatively, the security feature can be disabled with the following instructions: <https://learn.microsoft.com/en-us/windows/security/threat-protection/block-untrusted-fonts-in-enterprise>